



# Cisco SD-WAN (Viptela) vManage Help for Cisco IOS XE SD-WAN Release 16.9.x and Cisco SD-WAN Release 18.3.x



THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

All printed copies and duplicate soft copies of this document are considered uncontrolled. See the current online version for the latest version.

Cisco has more than 200 offices worldwide. Addresses and phone numbers are listed on the Cisco website at [www.cisco.com/go/offices](http://www.cisco.com/go/offices).

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: [www.cisco.com/go/trademarks](http://www.cisco.com/go/trademarks). Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1721R)



ADMINISTRATION.....	4
CONFIGURATION .....	24
DASHBOARD.....	255
MAINTENANCE .....	264
MONITOR.....	272
TOOLS .....	302
VANALYTICS .....	307
VMANAGE NMS PRODUCT HELP .....	315

## Administration

### Cluster Management

Use the Cluster Management screen to create a vManage NMS cluster. In a vManage NMS cluster, all the cluster members communicate and work cooperatively to manage all the vBond orchestrators, vEdge routers, and vSmart controllers in the overlay network. Each vManage server can manage up to about 2,000 vEdge routers in the overlay network.

It is strongly recommended that all members of a vManage NMS cluster be located in the same data center.

### Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Cluster Management.
- Service Configuration bar—Includes tabs for Service Configuration and Service Reachability.
  - Service Configuration tab—Display the configured vManage NMSs and cluster services configured on each vManage NMS. When you first open the Cluster Management screen, the Service Configuration tab is selected.
    - Add vManage button—Add a new vManage NMS to a cluster.
  - Service Reachability tab—Display the reachable cluster services reachable on the vManage NMSs in the cluster.
    - Current vManage—Display the IP address of the vManage NMS you are currently logged into.
- Status legend—Includes colored icons for Normal, Warning, Error, and Disabled.
- Table of vManage NMS cluster members—Click a green check mark in the table to display which cluster members are reporting the status. To re-arrange the columns, drag the column title to the desired position.

The screenshot shows the Cisco vManage Administration (Cluster Management) screen. The interface includes a sidebar menu on the left with 'Administration' selected. The main content area is titled 'ADMINISTRATION (CLUSTER MANAGEMENT)' and has two tabs: 'Service Configuration' (active) and 'Service Reachability'. A table displays three vManage NMS cluster members, all with a 'Ready' status. A status legend at the top right shows icons for Normal (green), Warning (yellow), Error (red), and Disabled (grey).

Hostname	IP Address	Status	Application Ser.	Business Data	Configuration D.	Messaging Ser.	Load Balance	USB
vms001	172.172.1.2	Ready	✓	✓	✓	✓	⊘	aaa7e7f11-3a6b...
vms002	172.172.3.2	Ready	✓	✓	✓	✓	⊘	17228f50-8126...
vms003	172.172.2.2	Ready	✓	✓	✓	✓	⊘	5bf52499-4b8d...

## Change the IP Address of the Current vManage NMS

It is recommended that you configure the IP address of the vManage server statically, in its configuration file. Configure this IP address on a non-tunnel interface in VPN 0. It is also recommended that you do not configure DHCP in VPN 512.

When you start a vManage NMS for the first time, the default IP address of the vManage server is shown as "localhost". Before you can add a new vManage NMS to a cluster, you must change "localhost" to an IP address:

1. In the Service Configuration tab, click the Add vManage button. The Edit vManage screen opens.
2. From the vManage IP Address drop-down list, select an IP address to assign to the vManage server.
3. Specify a username and password for the vManage server.
4. Click Update.

The vManage server automatically reboots and displays the Cluster Management screen.

## Add a vManage NMS

To add a new vManage NMS to the cluster:

1. In the Service Configuration tab, click the Add vManage button. The Add vManage screen opens.
2. Enter the IP address of the vManage NMS you are adding to the cluster.

Note: It is strongly recommended that the IP addresses of all members of the vManage cluster be in the same subnet.

3. Specify the username and password for the new vManage server.
4. Select the services to run on the vManage server. You can select from the services listed below.  
Note that the Application Server field is not editable. The vManage Application Server is the local vManage HTTP web server.
  - Statistics Database—Stores all real-time statistics from all Viptela devices in the network.
  - Configuration Database—Stores all the device and feature templates and configurations for all Viptela devices in the network.
  - Messaging Server—Distributes messages and shares state among all vManage NMS cluster members.
5. Click Add. The vManage NMS that you just added then reboots before joining the cluster.

In a cluster, it is recommended that you run at least three instances of each service.

Note: The members of a vManage cluster rely on timestamps to synchronize data and to track device uptime. For this time-dependent data to remain accurate, you cannot change the clock time on any one of the vManage servers of the cluster after you create the cluster.

## Configure the Statistics Database

To configure the statistics database, which stores all real-time statistics from the local vManage NMS:

1. In the Service Configuration tab, click the Statistics Database Configuration button. The Statistics Database Configuration screen opens. The top of the screen specifies the maximum space available for the database.
2. For each Statistics Type field, assign an amount of storage to allocate, in gigabytes (GB). The total value of all fields cannot exceed the maximum available space.
3. Click Update.

vManage NMS updates the storage allocations you have assigned once a day, at midnight.

## View Statistics Database Space Usage

To view the amount of space available and utilized for the statistics database on the local vManage NMS, in the Service Configuration tab, click the Statistics Database Configuration button. The Statistics Database Configuration screen opens. The top of the screen shows the maximum space available for the database and the total amount of space currently being utilized. The table on this screen shows, for each statistics type, the disk space currently being utilized.

## View vManage Service Details

To view detailed information about the services running on a vManage NMS:

1. In the Service Configuration tab, click on the hostname of the vManage server. The IP Address screen opens, with the vManage Details tab selected. This screen displays the process IDs of all the vManage services that are enabled on the vManage NMS.
2. Click Cluster Management in the breadcrumb in the title bar to return to the Cluster Management screen.

## View Devices Connected to a vManage NMS

To view a list of devices connected to a vManage NMS:

1. In the Service Configuration tab, click on the hostname of the vManage server. The IP Address screen opens with the vManage Details tab selected.
2. Click the Connected Device tab to view a detailed list of all devices connected to the vManage NMS.

Alternatively:

1. In the Service Configuration tab, for a vManage NMS, click the More Actions icon to the right of its row.
2. Click Device Connected.

## Edit a vManage NMS

1. In the Service Configuration tab, for a vManage NMS, click the More Actions icon to the right of its row and click Edit. The Edit vManage screen opens.
2. In the vManage IP Address box, select the IP address to edit.
3. Enter the username and password, and edit the cluster services provided by that vManage NMS.
4. Click Update.

## Remove a vManage NMS from the Cluster

1. In the Service Configuration tab, for a vManage NMS, click the More Actions icon to the right of its row and click Remove. The Remove vManage dialog box opens.
2. Enter the username and password to confirm removal of the device from the network.
3. Click Remove.

The vManage NMS is removed from the cluster, the device is invalidated, and the certificates for that device are deleted. The remaining members in the cluster re-balance the NMS services.

## View Available Cluster Services

To view the services that are available and reachable on all members in the vManage NMS cluster, click the Service Reachability tab.

## Additional Information

[Create a vManage Cluster](#)


## Manage Users

Use the Manage Users screen to add, edit, or delete users and user groups from the vManage NMS.

Only a user logged in as the **admin** user or a user who has Manage Users write permission can add, edit, or delete users and user groups from the vManage NMS.

## Screen Elements

- **Top bar**—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- **Title bar**—Includes the title of the screen, Manage Users.
- **Users tab**—Add, edit, or delete users who are allowed to perform operations on the vManage NMS.
  - **Add User:** Add a new user.
  - **Search box:** Includes the Search Options drop-down, for a Contains or Match string.
  - **Refresh icon:** Click to refresh data in the device table with the most current data.
  - **Table with list of users:** To re-arrange the columns, drag the column title to the desired position.
- **User Groups tab**—Add, edit, or delete user groups.
  - **Add User Group:** Add a user group.
  - **Group Name:** Search for a user group. The list of user groups are displayed directly beneath Group Name in the left pane.
  - **Edit:** Edit the privilege levels for the selected user group.
  - **Privilege level table:** Displays privilege levels for the user group selected in the Group Name field.



## Add a User

To perform operations on a Viptela device, you configure usernames and passwords for users who are allowed to access the Viptela device. The Viptela software provides one standard username, **admin**, and you can also create custom usernames, as needed.

To add a user:

1. In the Users tab, click Add User.
2. In the Add User popup window, enter the full name, username, and password for the user. Note that uppercase characters are not allowed in usernames.
3. From the User Groups drop-down list, select the groups that the user will be a member of.
4. Click Add. The user is then listed in the user table.

## Delete a User

1. In the Users tab, select the user you wish to delete.
2. Click the More Actions icon to the right of the column and click Delete.
3. Click OK to confirm deletion of the user.

## Edit User Details

1. In the Users tab, select the user whose details you wish to edit.
2. Click the More Actions icon to the right of the column and click Edit.
3. Edit login details, and add or remove the user from user groups.



4. Click Update.

## Change User Password

1. In the Users tab, select the user whose password you wish to change.
2. Click the More Actions icon to the right of the column and click Change Password.
3. Enter, and then confirm, the new password. Note that the user, if logged in, is logged out.
4. Click Done.

## Add a User Group

Users are placed in groups, which define the specific configuration and operational commands that the users are authorized to view and modify. A single user can be in one or more groups. The Viptela software provides three standard user groups, and you can also create custom user groups, as needed:

- **basic**—Includes users who have permission to view interface and system information.
- **netadmin**—Includes the admin user, by default, who can perform all operations on the vManage NMS. You can add other users to this group.
- **operator**—Includes users who have permission only to view information.

To add a user group:

1. In the User Groups tab, click Add User Group.
2. In the Add User Group popup window, enter the user group name and select the desired read and write permissions for each feature. Note that uppercase characters are not allowed in user group names.
3. Click OK. The user group is then listed in the left pane.

Each user group can have read or write permission for the features listed below. Write permission includes read permission.

Note: All user groups, regardless of the read or write permissions selected, can view the information displayed in the vManage Dashboard screen.

Feature	Read Permission	Write Permission
Alarms	Set alarm filters and view alarms generated on Viptela devices on the Monitor ► Alarms screen.	No additional permissions.
Audit Log	Set audit log filters and view a log of all activities on Viptela devices on the Monitor ► Audit Log screen.	No additional permissions.
Certificates	View a list of vEdge routers in the overlay network on the Configuration ► Certificates ► vEdge List screen.  View a CSR and certificate on the Configuration ► Certificates ► Controllers screen.	Validate and invalidate a vEdge router, stage a vEdge router, and send the serial number of valid controller devices to the vBond orchestrator on the Configuration ► Certificates ► vEdge List screen.  Generate a CSR, install a signed certificate, reset the RSA key pair, and invalidate a controller device on the Configuration ► Certificates ► Controllers screen.

Cluster	View information about services running on a vManage NMS, a list of devices connected to a vManage NMS, and the services that are available and running on all the vManage NMSs in the cluster on the Administration ► Cluster Management screen.	Change the IP address of the current vManage NMS, add a vManage NMS to the cluster, configure the statistics database, edit a vManage NMS, and remove a vManage NMS from the cluster on the Administration ► Cluster Management screen.
Device Inventory	View a vEdge router's running and local configuration, a log of template activities, and the status of attaching configuration templates to vEdge routers on the Configuration ► Devices ► vEdge List screen.  View the running and local configuration of a controller device, a log of template activities, and the status of attaching configuration templates to controller devices on the Configuration ► Devices ► Controllers screen.	Upload the vEdge router authorized serial number file to the vManage NMS, toggle a vEdge router from vManage configuration mode to CLI mode, copy a vEdge router's configuration, and delete a vEdge router from the network on the Configuration ► Devices ► vEdge List screen.  Add and delete controller devices from the overlay network, and edit the IP address and login credentials of a controller device on the Configuration ► Devices ► Controllers screen.
Device Monitoring	View the geographic location of Viptela devices on the Monitor ► Geography screen.  View events that have occurred on Viptela devices on the Monitor ► Events screen.  View a list of Viptela devices in the network, device status summary, DPI flow information, TLOC loss, latency, and jitter information, control and tunnel connections, system status, and events on the Monitor ► Network screen (only if System is selected).	Ping a device, run a traceroute, and analyze the traffic path for an IP packet on the Monitor ► Network ► Troubleshooting screen (only if System is selected).
Device Reboot	View a list of devices on which the reboot operation can be performed on the Maintenance ► Device Reboot screen.	Reboot one or more Viptela device on the Maintenance ► Device Reboot screen.
Interface	View information about interfaces on a device on the Monitor ► Network ► Interface screen (only if Device Monitoring is selected).	Edit Chart Options to select the type of data to display, and edit the time period for which to display data on the Monitor ► Network ► Interface screen (only if Device Monitoring is selected).
Manage Users	View users and user groups on the Administration ► Manage Users screen.	Add, edit, and delete users and user groups from the vManage NMS, and edit user group privileges on the Administration ► Manage Users screen.
Policy	View common policies for all vSmart controllers or vEdge routers in the network on the Configuration ► Policy screen (only if Policy Configuration and Policy Deploy are selected).	Create, edit, and delete common policies for all vSmart controllers or vEdge routers in the network on the Configuration ► Policy screen (only if Policy Configuration and Policy Deploy are selected).
Policy Configuration	View list of policies created and details about them on the Configuration ► Policy screen (only if Policy is selected).	Create, edit, and delete common policies for all vSmart controllers and vEdge routers in the network on the Configuration ► Policy screen (only if Policy is selected).
Policy Deploy	View the current status of the vSmart controllers to which a policy is being applied on the Configuration ► Policy screen (only if Policy is selected).	Activate and deactivate common policies for all vSmart controllers in the network on the Configuration ► Policy screen (only if Policy is selected).
Routing	View real-time routing information for a device on the Monitor ► Network ► Real-Time screen (only if Device Monitoring is selected).	Add command filters to speed up the display of information on the Monitor ► Network ► Real-Time screen (only if Device Monitoring is selected).

Settings	View the organization name, vBond DNS/IP address, certificate authorization settings, software version enforced on a vEdge router, custom banner on the vManage login screen, and the current settings for collecting statistics on the Administration ► Settings screen.	Edit the organization name, vBond DNS/IP address, certificate authorization settings, software version enforced on a vEdge router, custom banner on the vManage login screen, current settings for collecting statistics, generate a Certificate Signing Request (CSR) for a web server certificate, and install a certificate on the Administration ► Settings screen.
Software Upgrade	View a list of Viptela devices on which software upgrade can be performed and the current software version running on a device on the Maintenance ► Software Upgrade screen.	Upload new software images on Viptela devices, upgrade, activate, and delete a software image on a device, and set a software image to be the default image on a Viptela device on the Maintenance ► Software Upgrade screen.
System	View system-wide parameters configured using vManage templates on the Configuration ► Templates ► System screen (only if Device Monitoring is selected).	Configure system-wide parameters using vManage templates on the Configuration ► Templates ► System screen (only if Device Monitoring is selected).
Template Configuration	View feature and device templates on the Configuration ► Templates screen.	Create, edit, delete, and copy a feature or device template on the Configuration ► Templates screen.
Template Deploy	View devices attached to a device template on the Configuration ► Templates screen.	Attach a device to a device template on the Configuration ► Templates screen.
Tools	Use the Admin Tech command to collect system status information for a device on the Tools ► Operational Commands screen.	Use the Admin Tech command to collect system status information for a device, and use the Interface Reset command to shut down and then restart an interface on a device in a single operation on the Tools ► Operational Commands screen.  Rediscover the network to locate new devices and synchronize them with the vManage NMS on the Tools ► Rediscover Network screen.  Establish an SSH session to a Viptela device and issue CLI commands on the Tools ► SSH Terminal screen.

## Delete a User Group

1. In the User Groups tab, click the name of the user group you wish to delete. Note that you cannot delete any of the three standard user groups—basic, netadmin, and operator.
2. Click the Trash icon.
3. Click OK to confirm deletion of the user group.

## Edit User Group Privileges

1. In the User Groups tab, select the name of the user group whose privileges you wish to edit. Note that you cannot edit privileges for the three standard user groups—basic, netadmin, and operator.
2. Click the Edit button located directly above the privilege level table, and edit privileges as needed.
3. Click Save.

If an **admin** user changes the privileges of a user by changing their group, and if that user is currently logged in to the device, the user is logged out and must log back in again.

## Settings

Use the Settings screen to view the current settings and configure the setting for vManage NMS parameters, including the organization name, vBond orchestrator's DNS name or IP address, certificate settings, and statistics collection.

The current setting for each item is displayed in the bar for each item, immediately following the name.

## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Settings.
- Organization Name bar—Click View to view the organization name or Edit to edit the name.
- vBond bar—Click View to view the vBond DNS/IP address or Edit to enter new values.
- Email Notifications bar—Click View to view the settings for email notifications from the vManage server.
- Controller Certificate Authorization bar—Click View to view the certificate authorization settings or Edit to edit the settings.
- vEdge Cloud Certificate Authorization bar—Click View to view the vEdge Cloud certification authorization setting or Edit to edit the setting.
- Web Server Certificate bar—Click CSR to generate a Certificate Signing Request (CSR) for a web server certificate or Certificate to install the certificate.
- Enforce Software Version (ZTP) bar—Click View to view the software version enforced on a vEdge router or Edit to enforce a software version on the router.
- Banner bar—Click View to view the custom banner on the vManage login screen or Edit to edit or create a custom banner.
- Reverse Proxy bar—Click View to view the current settings for reverse proxy or Edit to edit the settings.
- Statistics Setting bar—Click View to view the current settings for collecting device statistics or Edit to edit the settings.
- Cloud onRamp bar—Click View to view the current settings for Cloud onRamp service or Edit to edit the setting.
- vAnalytics bar—Click View to view the current settings for the vAnalytics platform or Edit to edit the setting.
- Client Session Timeout bar—Click View to view the current vManage client session timeout setting or Edit to edit the setting.
- Identity Provider Settings—Click View to view the current vManage identity provider setting or Edit to edit the setting.
- Data Stream bar—Click View to view the current data streaming setting or Edit to edit the setting.
- Tenancy Mode bar—Click View to view the current tenancy setting or Edit to edit the setting.
- Statistics Configuration bar—Click View to view the current time interval for collecting device statistics or Edit to edit the setting.
- Maintenance Window bar—Click Edit to configure a maintenance time window notification.
- Statistics Database Configuration bar—Click View to view the current the vManage statistics database setting or Edit to edit the settings.

ADMINISTRATION   SETTINGS		
Organization Name	viPtela Inc Regression	View
vBond	10.0.12.26 : 12346	View   Edit
Email Notifications	Disabled	View   Edit
Controller Certificate Authorization	Manual	View   Edit
vEdge Cloud Certificate Authorization	Automated	View   Edit
Web Server Certificate	04 Nov 2019 9:07:40 AM	CSR   Certificate
Enforce Software Version (ZTP)		View   Edit
Banner	Disabled	View   Edit
Reverse Proxy	Disabled	View   Edit
Statistics Setting		View   Edit
CloudExpress	Enabled	View   Edit
vAnalytics	Disabled	View   Edit
Client Session Timeout	Disabled	View   Edit
Data Stream	Disabled	View   Edit
Tenancy Mode	Single Tenant	View   Edit
Statistics Configuration	Collection Interval: 30 minutes	View   Edit
Maintenance Window	Not Configured	Edit
Identity Provider Settings	Disabled	View   Edit
Statistics Database Configuration	Maximum Available Space: 17.7176 GB	View   Edit
Google Map API Key	Maps API Key: AlzaSyA1PwZaBfTR4-PLCErEs16qMFEiqnRV898	View   Edit
Software Install Timeout	Collection Interval: 60 minutes	View   Edit

## Configure Organization Name

Before you can generate a CSR, you must configure the name of your organization. The organization name is included in the CSR.

To configure the organization name:

1. Click the Edit button to the right of the Organization Name bar.
2. In the Organization Name field, enter the name of your organization. The organization name must be identical to the name that is configured on the vBond orchestrator.
3. In the Confirm Organization Name field, re-enter and confirm your organization name.
4. Click Save.

Note that once the control connections are up and running, the organization name bar is not editable.

## Configure vBond DNS Name or IP Address

1. Click the Edit button to the right of the vBond bar.
2. In the vBond DNS/IP Address: Port field, enter the DNS name that points to the vBond orchestrator or the IP address of the vBond orchestrator and the port number to use to connect to it.
3. Click Save.

## Enable Email Notifications

You can configure the vManage NMS to send email notifications when alarms occur on devices in the overlay network. First configure the SMTP and email recipient parameters on this screen:

1. Click the Edit button to the right of the Email Notifications bar.
2. In the Enable Email Notifications field, click Enabled.
3. Select the security level for sending the email notifications. The security level can be none, SSL, or TLS.
4. In the SMTP Server field, enter the name or IP address of the SMTP server to receive the email notifications.
5. In the SMTP port field, enter the SMTP port number. For no security, the default port is 25; for SSL it is 465; and for TLS it is 587.
6. In the From Address field, enter the full email address to include as the sender in email notifications.
7. In the Reply To address, enter the full email address to include in the Reply-To field of the email. This address can be a noreply address, such as noreply@cisco.com.
8. To enable SMTP authentication to the SMTP server, click Use SMTP Authentication. Enter the username and password to use for SMTP authentication. The default user email suffix is appended to the username. The password that you type is hidden.
9. Click Save.

Then configure the alarms that trigger emails by clicking the Email Notifications button on the Monitor ► Alarms screen.

## Configure Controller Certificate Authorization Settings

Signed certificates are used to authenticate devices in the overlay network. Once authenticated, devices can establish secure sessions between each other. It is from the vManage NMS that you generate these certificates and install them on the controller devices—vBond orchestrators, vManage NMSs, and vSmart controllers. You can use certificates signed by Symantec, or you can use enterprise root certificates.

The controller certification authorization settings establish how the certification generation for all controller devices will be done. They do not generate the certificates.

You need to select the certificate-generation method only once. The method you select is automatically used each time you add a device to the overlay network.

To have the Symantec signing server automatically generate, sign, and install certificates on each controller device:

1. Click the Edit button to the right of the Controller Certificate Authorization bar.
2. Click Symantec Automated (Recommended). This is the recommended method for handling controller signed certificates.
3. In the Confirm Certificate Authorization Change popup, click Proceed to confirm that you wish to have the Symantec signing server automatically generate, sign, and install certificates on each controller device.
4. Enter the first and last name of the requestor of the certificate.

## Administration

5. Enter the email address of the requestor of the certificate. This address is required because the signed certificate and a confirmation email are sent to the requestor via email; they are also made available through the customer portal.
6. Specify the validity period for the certificate. It can be 1, 2, or 3 years.
7. Enter a challenge phrase. The challenge phrase is your certificate password and is required when you renew or revoke a certificate.
8. Confirm your challenge phrase.
9. In the Certificate Retrieve Interval field, specify how often the vManage server checks if the Symantec signing server has sent the certificate.
10. Click Save.

To manually install certificates that the Symantec signing server has generated and signed:

1. Click the Edit button to the right of the Controller Certificate Authorization bar.
2. Click Symantec Manual.
3. In the Confirm Certificate Authorization Change popup, click Proceed to manually install certificates that the Symantec signing server has generated and signed.
4. Click Save.

To use enterprise root certificates:

1. Click the Edit button to the right of the Controller Certificate Authorization bar.
2. Click Enterprise Root Certificate.
3. In the Confirm Certificate Authorization Change popup, click Proceed to confirm that you wish to use enterprise root certificates.
4. In the Certificate box, either paste the certificate, or click Select a file and upload a file that contains the enterprise root certificate.
5. By default, the enterprise root certificate has the following properties:
  - Country: United States
  - State: California
  - City: San Jose
  - Organizational unit: viPtela Inc Regression
  - Organization: viPtela Inc
  - Domain name: viptela.com
  - Email: [support@viptela.com](mailto:support@viptela.com)

To view this information, issue the [show certificate signing-request decoded](#) command on a controller device, and check the output in the Subject line. For example:

```
vSmart# show certificate signing-request decoded
...
Subject: C=US, ST=California, L=San Jose, OU=viPtela Inc Regression, O=viPtela Inc, CN=vsmart- uuid
.viptela.com/emailAddress=support@viptela.com
...
vSmart#
```

To change one or more of the default CSR properties:

- a. Click Set CSR Properties.
- b. Enter the domain name to include in the CSR. This domain name is appended to the certificate number (CN).
- c. Enter the organizational unit (OU) to include in the CSR.
- d. Enter the organization (O) to include in the CSR.
- e. Enter the city (L), state (ST), and two-letter country code (C) to include in the CSR.

- f. Enter the email address (emailAddress) of the certificate requestor.
  - g. Specify the validity period for the certificate. It can be 1, 2, or 3 years.
6. Click Import & Save.

## Configure vEdge Cloud Certificate Authorization Settings

Certificates are used to authenticate vEdge Cloud routers in the overlay network. Once authentication is complete, vEdge Cloud routers can establish secure sessions with other devices in the overlay network.

By default, vEdge Cloud certification authorization is automated. This is the recommended setting.

If you use third-party certificate authorization, configure certificate authorization to be manual:

1. Click the Edit button to the right of the vEdge Cloud Certificate Authorization bar.
2. In the vEdge Cloud field, click Manual (Enterprise CA).
3. Click Save.

## Generate Web Server Certificate

To establish a secure connection between your web browser and the vManage server using authentication certificates, generate a CSR to create a certificate, have it signed by a root CA, and then install it. To do so:

1. Click the CSR button to the right of the Web Server Certificate bar.
2. In the Common Name field, enter the domain name or IP address of the vManage server. For example, the fully-qualified domain name of vManage could be vmanage.org.local.
3. In the Organizational Unit field, enter the unit name within your organization, for example, Network Engineering.
4. In the Organization field, enter the exact name of your organization as specified by your root CA, for example, Viptela Inc.
5. In the City field, enter the name of the city where your organization is located, for example, San Jose.
6. In the State field, enter the state in which your city is located, for example, California.
7. In the 2-Letter Country Code field, enter the two-letter code for the country in which your state is located. For example, the two-letter country code for the United States of America is US.
8. From the Validity drop-down, select the validity period for the certificate.
9. Click Generate to generate the CSR.
10. Send the CSR to Symantec or a root CA for signing.
11. When you receive the signed certificate, click the Certificate button to the right of the Web Server Certificate bar to install the new certificate. The View box displays the current certificate on the vManage server.
12. Copy and paste the new certificate in the box. Or click the Import button, click Select a File to download the new certificate file, and click Import.
13. Once the certificate is installed, reboot the vManage server.

Below is an example of a certificate generated with the above configuration. Note that the certificate is truncated in this example.





4. From the Software Version drop-down, select the version of the software to enforce on vEdge routers when they join the network.
5. Click Save.

If you enable this feature on the vManage NMS, any vEdge router joining the network is configured with the version of the software specified in the Enforce Software Version field regardless of whether the router was running a higher or lower version of Viptela software.

## Create a Custom Banner

To create a custom banner that is displayed after you log in to the vManage NMS:

1. Click the Edit button to the right of the Banner bar.
2. In the Enable Banner field, click Enabled.
3. In the Banner Info text box, enter the text string for the login banner or click Select a File to download a file that contains the text string.
4. Click Save.

## Enable Reverse Proxy

To enable reverse proxy services in the overlay network:

1. Click the Edit button to the right of the Reverse Proxy bar.
2. Click Enabled.
3. Click Save.

To configure reverse proxy on individual vManage NMS and vSmart controller devices, in vManage NMS select Configuration ► Devices and then click the Controllers tab. For the desired device, click the More Actions icon to the right of the row, and click Add Reverse Proxy. Then configure the private and proxy IP addresses and ports for the device.

For more information, see [Enable Reverse Proxy](#).

## Collect Device Statistics

To enable or disable the collection of statistics for devices in the overlay network:

1. Click the Edit button to the right of the Statistics Settings bar. By default, all statistics collection settings are enabled for all Viptela devices.
2. To set statistics collection parameters for all devices in the network, click Disable All for the parameter you wish to disable statistics collection for.  
To return to the saved settings during an edit operation, click Reset.  
To return the saved settings to the factory-default settings, click Restore Factory Default
3. To set statistics collection parameters for individual devices in the network, click Custom to select devices on which to enable or disable statistics collection. The Select Devices popup screen opens listing the hostname and device IP of all devices in the network. Select one or more devices from the Enabled Devices column on the left and click the arrow pointing right to move the device to the Disabled Devices column on the right. To move devices from the Disabled Devices to the Enabled Devices column, select one or more devices and click the arrow pointing left. To select all devices in the Select Devices popup screen, click the Select All checkbox in either window. Click Done when all selections are made.
4. Click Save.

## Enable Cloud onRamp Service

1. Click the Edit button to the right of the Cloud onRamp bar.
2. In the Enable Cloud onRamp field, click Enabled.
3. Click Save.

## Enable vAnalytics Platform

1. Click the Edit button to the right of the vAnalytics bar.
2. In the Enable vAnalytics field, click Enabled.
3. Click Save.

## Enable vManage Client Session Timeout

By default, a user's session to a vManage client remains established indefinitely and never times out. To set how long a vManage client session is inactive before a user is logged out:

1. Click the Edit button to the right of the Client Session Timeout bar.
2. In the Session Timeout field, click Enabled.
3. In the Timeout field, enter the timeout value, in minutes. This value can be from 10 to 180 minutes.
4. Click Save.

The client session timeout value applies to all vManage servers in a vManage cluster.

## Enable Single Sign-On

To enable single sign-on (SSO) for the vManage NMS to allow users to be authenticated using an external identity provider:

1. Ensure that you have enabled NTP on the vManage NMS.
2. Click the Edit button to the right of the Identity Provider Settings bar.
3. In the Enable Identity Provider field, click Enabled,
4. Copy and paste the identity provider metadata in the Upload Identity Provider Metadata box. Or click Select a File to upload the identity provider metadata file.
5. Click Save.

## Enable Data Stream Collection

By default, collecting streams of data from a network device is not enabled. To use the Packet Capture, Speed Test, and Debug Logs troubleshooting tools, you must enable the collection of data streams.

To collect data streams:

1. Click the Edit button to the right of the Data Stream bar.

2. In the Data Stream field, click Enabled.
3. In the Hostname field, enter the name of the host to which to send the collected data. Enter just the hostname (such as "test") with no domain name. It is recommended that this host be one that is used for out-of-band management and that is located in the management VPN.
4. In the VPN field, enter the number of the VPN in which the host is located. It is recommended that this be the management VPN, which is typically VPN 512.
5. Click Save.

## Set the Tenancy Mode

By default, the vManage server is in single tenant mode, which enables it to manage a single overlay network. To place the vManage server in multitenant mode so that you can manage the overlay networks of multiple tenants:

1. Click the Edit button to the right of the Tenancy Mode bar.
2. In the Tenancy field, click Multitenant.
3. In the Domain field, enter the domain name for the service provider (for example, viptela.com).
4. Click Save. The vManage server reboots and comes back up in multitenant mode.

Note: After you place a vManage server into multitenant mode, you cannot convert it back to single-tenant mode.

To configure tenants, go to the Administration ► Tenant Management screen.

## Set Interval to Collect Device Statistics

To set the time interval at which vManage NMS should collect statistics for devices in the overlay network:

1. Click the Edit button to the right of the Statistics Configuration bar. By default, statistics is collected for all Viptela devices every 30 minutes.
2. Click the up or down arrow in the Collection Interval drop-down to change the frequency at which to collect device statistics. The minimum time you can specify is 5 minutes and the maximum is 180 minutes.
3. Click Save.

## Configure a Maintenance Window

To configure a maintenance window for the vManage server:

1. Click the Edit button to the right of the Maintenance Window bar.
2. Click the Start date and time drop-down, and select the date and time when the maintenance window will start.
3. Click the End date and time drop-down, and select the date and time when the maintenance window will end.
4. Click Save. The start and end times and the duration of the maintenance window are displayed in the Maintenance Window bar.

Two days before the start of the window, the vManage Dashboard displays a maintenance window alert notification.

To cancel a maintenance window for the vManage server:

1. Click the Edit button to the right of the Maintenance Window bar.

2. Click Cancel maintenance window.

## Configure the vManage Statistics Database

To configure the vManage statistics database, which stores all real-time statistics from the local vManage NMS:

1. Click the Edit button to the right of the Statistics Database Configuration bar. The Statistics Database Configuration screen opens. The Statistics Database Configuration bar shows the maximum space available for the database.
2. For each Statistics Type row, enter the maximum size of the statistics file, in gigabytes (GB). The total value of all fields cannot exceed the maximum available space.
3. Click Save.

vManage NMS updates the storage allocations you have assigned once a day, at midnight.

To view the actual and maximum size of statistics database on the vManage server:


1. Click the Edit button to the right of the Statistics Database Configuration bar. The Statistics Database Configuration screen opens. The table on this screen shows, for each statistics type, the disk space currently being utilized.
2. Click Close.

## Tenant Management

Use the Tenant Management screen to add tenants to a vManage server that is operating in multitenant mode.

### Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. In the middle is the name of the provider and the Select Tenant drop-down. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Tenant Management.
- Add Tenant button—Add a new tenant to the provider's domain.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- All tenants—The left pane lists all the tenants.
- Tenant—The right pane shows information for the tenant selected in the left pane.



## Add a Tenant

1. In the left pane, click the Add Tenant button.
2. In the Add Tenant window:
  - a. Enter a name for the tenant. It can be up to 128 characters and can contain only alphanumeric characters.
  - b. Enter a description for the tenant. It can be up to 256 characters and can contain only alphanumeric characters.
  - c. Enter the name of the organization. The name is case-sensitive. It is the name in the certificates for all Viptela network devices, and it must be identical on all devices in the overlay network.
  - d. In the URL subdomain field, enter the domain name for the tenant. The domain name must include the provider's domain name. For example, for the provider viptela.com, a valid domain name might be plum.viptela.com. You must also configure this same domain name when you enable multitency mode, in vManage Administration ► Settings ► Tenancy Mode.
  - e. Click Save.
3. The Create Tenant screen is displayed, and the Status column shows In progress. To view status messages related to the creation of the tenant, click the > to the left of the status column. After about 1 minute, the Status column changes to Success, and the tenant table shows the tenant's system IP address.

## View All Tenants

To view a summary of information about all tenants, in the center of the top bar, click the provider name.

## View a Single Tenant

To view a summary of information about a single tenant:

## Administration

1. In the center of the top bar, click the provider name.
2. In the table of tenants, click the tenant name. The summary information displays to the right of the name.
3. To hide the summary information, click the tenant name a second time.

To view the vManage dashboard for a single tenant:

1. In the center of the top bar, click Select Tenant to the right of the provider name.
2. Select the tenant name from the drop-down.

## Edit a Tenant

1. In the left pane, click the name of the tenant.
2. In the right pane, click the Pencil icon to the right of the tenant's name.
3. In the Edit Tenant popup, modify the tenant's name, description, or domain name.
4. Click Save.

## Remove a Tenant

1. In the left pane, click the name of the tenant.
2. In the right pane, click the Trash icon to the right of the tenant's name.
3. In the Delete Tenant popup, enter your vManage password and click Save.

## Additional Information

[Multitenant Dashboard](#)

[Use a Multitenant vManage NMS](#)

## Configuration

### Certificates

Use the Certificates screen to manage certificates and authenticate WAN edge and controller devices in the overlay network.

Two components of the Viptela solution provide device authentication:

- Signed certificates are used to authenticate devices in the overlay network. Once authenticated, devices can establish secure sessions between each other. It is from the vManage NMS that you generate these certificates and install them on the controller devices—vManage NMSs, vBond orchestrators, and vSmart controllers.
- WAN edge authorized serial number file contains the serial numbers of all valid vEdge and WAN routers in your network. You receive this file from Viptela, mark each router as valid or invalid, and then from the vManage NMS, send the file to the controller devices in the network.

You must install the certificates and the WAN edge authorized serial number file on the controller devices to allow the Viptela overlay network components to validate and authenticate each other and thus to allow the overlay network to become operational.

Note: For purposes of certificate management, the term *controller* is used to collectively refer to the vManage NMS, the vSmart controller, and the vBond orchestrator.

### Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Certificates.
- WAN Edge List tab—Install the router authorized serial number file on the controllers in the overlay network and manage the serial numbers in the file. When you first open the Certificates screen, the WAN Edge List tab is selected.
  - Send to Controllers—Send the WAN edge router chassis and serial numbers to the controllers in the network.
  - Table of WAN edge routers in the overlay network—To re-arrange the columns, drag the column title to the desired position.
- Controllers tab—Install certificates and download the device serial numbers to the vBond orchestrator.
  - Send to vBond—Send the controller serial numbers to the vBond orchestrator.
  - Install Certificate—Install the signed certificates on the controller devices. This button is available only if you select Manual in Administration ► Settings ► Certificate Signing by Symantec.
  - Export Root Certificate—Display a copy of the root certificate for the controller devices that you can download to a file.
  - Table of controller devices in the overlay network—To re-arrange the columns, drag the column title to the desired position.
  - Certificate status bar—Located at the bottom of the screen, this bar is available only if you select Server Automated in Administration ► Settings ► Certificate Authorization. It displays the states of the certificate installation process:
    - Device Added
    - Generate CSR
    - Waiting for Certificate
    - Send to Controllers

A green check mark indicates that the step has been completed. A grey check mark indicates that the step has not yet been performed.



## Configuration

- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Refresh icon—Click to refresh data in the device table with the most current data.
- Export icon—Click to download all data to a file, in CSV format.
- Show Table Fields icon—Click the icon to display or hide columns from the device table. By default, all columns are displayed.

The screenshot shows the Cisco vManage interface with the 'vEdge Routers Table' displayed. The table contains the following data:

State	Device Model	Chassis Number	Hostname	IP Address	Serial No./Token	Validate
Invalid	vEdge Cloud	57946bed-cef8-44df-b3d5-73f7b042796d	vm4	172.16.255.14	12345711	Invalid   Staging   Valid
Invalid	vEdge Cloud	5d7be9cc-cb63-4657-bcef-341ded1caa19	vm1	172.16.255.11	12345715	Invalid   Staging   Valid
Invalid	vEdge Cloud	009b48f4-4c79-407a-8260-763fc60b1669	vm11	172.16.255.21	12345703	Invalid   Staging   Valid
Invalid	vEdge Cloud	0d1fc0e5-ef04-4ba1-9079-6628bb77e96c	vm5	172.16.255.15	12345712	Invalid   Staging   Valid
Invalid	vEdge Cloud	9cc3f823-8716-4f42-817f-01b79460c490	vm6	172.16.255.16	12345709	Invalid   Staging   Valid

## Check the WAN Edge Router Certificate Status

In the WAN Edge List tab, check the Validate column. The status can be one of the following:

- Valid (shown in green)—The router's certificate is valid.
- Staging (shown in yellow)—The router is in the staging state.
- Invalid (shown in red)—The router's certificate is not valid.

## Validate a WAN Edge Router

When you add vEdge and WAN routers to the network using the Configuration ► Devices screen, you can automatically validate the routers and send their chassis and serial numbers to the controller devices by clicking the checkbox Validate the uploaded WAN Edge List and send to controllers. If you do not select this option, you must individually validate each router and send their chassis and serial numbers to the controller devices. To do so:

1. In the WAN Edge List tab, select the router to validate.

2. In the Validate column, click Valid.
3. Click OK to confirm the move to the valid state.
4. Repeat Steps 1 to 3 for each router you wish to validate.
5. Click the Send to Controllers button in the upper left corner of the screen to send the chassis and serial numbers of the validated routers to the controller devices in the network. vManage NMS displays the Push WAN Edge List screen showing the status of the push operation.

## Stage a WAN Edge Router

When you initially bring up and configure a WAN Edge router, you can place it in staging state using the vManage NMS. When the router is in this state, you can configure the router, and you can test that the router is able to establish operational connections with the vSmart controller and the vManage NMS.

After you physically place the router at its production site, you change the router's state from staging to valid. It is only at this point that the router joins the actual production network. To stage a router:

1. In the WAN Edge List tab, select the router to stage.
2. In the Validate column, click Staging.
3. Click OK to confirm the move to the staging state.
4. Click Send to Controllers in the upper left corner of the screen to sync the WAN edge authorized serial number file with the controllers. vManage NMS displays the Push WAN Edge List screen showing the status of the push operation.

## Invalidate a WAN Edge Router

1. In the WAN Edge List tab, select the router to invalidate.
2. In the Validate column, click Invalid.
3. Click OK to confirm the move to the invalid state.
4. Repeat Steps 1 to 3 for each router you wish to invalidate.
5. Click the Send to Controllers button in the upper left corner of the screen to send the chassis and serial numbers of the validated routers to the controller devices in the network. vManage NMS displays the Push WAN Edge List screen showing the status of the push operation.

## Send the Controller Serial Numbers to vBond Orchestrator

To determine which controllers in the overlay network are valid, the vBond orchestrator keeps a list of the controller serial numbers. The vManage NMS learns these serial numbers during the certificate-generation process.

To send the controller serial numbers to the vBond orchestrator:

1. In the Controllers tab, check the certificate status bar at the bottom of the screen. If the Send to Controllers check mark is green, all serial numbers have already been sent to the vBond orchestrator. If it is grey, you can send one or more serial numbers to the vBond orchestrator.
2. Click the Send to vBond button in the Controllers tab.  
A controller's serial number is sent only once to the vBond orchestrator. If all serial numbers have been sent, when you click the Send to

## Configuration

vBond button, an error message is displayed. To resend a controller's serial number, you must first select the device and then select Invalid in the Validity column.

After the serial numbers have been sent, click the Tasks icon in the vManage toolbar to display a log of the file download and other recent activities.

## Install Signed Certificate

If in Administration ► Settings ► Certificate Signing by Symantec, you selected the Manual option for the certificate-generation process, use the Install Certificate button to manually install certificates on the controller devices.

The vManage NMS supports enterprise certificates that do not exceed a file size of 16 KB. Larger files will shut down the ZTP operation. To ensure the successful installation of an enterprise certificate, make sure that the certificate does not exceed 16 KB and remove unnecessary certificates from the certificate chain.

After Symantec or your enterprise root CA has signed the certificates, they return the files containing the individual signed certificates. Place them on a server in your local network. Then install them on each controller:

1. In the Controllers tab, click the Install Certificate button.
2. In the Install Certificate window, select a file, or copy and paste the certificate text.
3. Click Install to install the certificate on the device.  
The certificate contains information that identifies the controller, so you do not need to select the device on which to install the certificate.
4. Repeat Steps 1 to 3 to install additional certificates.

## Export Root Certificate

1. In the Controllers tab, click the Export Root Certificate button.
2. In the Export Root Certificate window, click Download to export the root certificate to a file.
3. Click Close.

## View the CSR

1. In the WAN Edge List or Controllers tab, select a device.
2. Click the More Actions icon to the right of the row, and click View CSR to view the certificate signing request (CSR).

## View the Certificate

1. In the Controllers tab, select a device.
2. Click the More Actions icon to the right of the row and click View Certificate.

## Generate the CSR

1. In the Controllers tab, select a device.
2. Click the More Actions icon to the right of the row and click Generate CSR.

---

## Configuration

3. In the Generate CSR window, click Download to download the file to your local PC (that is, to the PC you are using to connect to the vManage NMS).
4. Repeat Steps 1 to 4 for each controller for which you are generating a CSR.

### Reset the RSA Key Pair

1. In the Controllers tab, select a device.
2. Click the More Actions icon to the right of the row and click Reset RSA.
3. Click OK to confirm resetting of the device's RSA key and to generate a new CSR with new public/private keys.

### Invalidate a Device

1. In the Controllers tab, select a device.
2. Click the More Actions icon to the right of the row and click Invalidate.
3. Click OK to confirm invalidation of the device.

### View Log of Certificate Activities

To view the status of certificate-related activities:

1. Click the Tasks icon located in the vManage toolbar. vManage NMS displays a list of all running tasks along with the total number of successes and failures.
2. Click a row to see details of a task. vManage NMS opens a status window displaying the status of the task and details of the device on which the task was performed.

### Cloud onRamp Dashboard

Use the Cloud onRamp dashboard to configure the Cloud onRamp for SaaS service and to view the performance of cloud applications for which you have enabled Cloud onRamp service.


Cloud onRamp service calculates a value called the Viptela Quality of Experience (vQoE). The vQoE value weighs loss and latency using a formula customized for each application. For example, email applications tolerate latency better than video applications do, and video applications tolerate loss better than email does. The vQoE value ranges from zero to ten, with zero being the worst quality and ten being the best. Cloud onRamp service computes vQoE values for applications and paths, then assigns applications to the paths that best match their vQoE value. Cloud onRamp service periodically recalculates vQoE values for paths to ensure ongoing optimal application performance.

### Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Cloud onRamp.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Application panes—Display performance of individual applications.
- Legend—Indicates quality of experience levels for cloud applications.

Configuration

- Manage Cloud onRamp—Manage Cloud onRamp applications, client sites, gateways, and Direct Internet Access (DIA) sites.



### View Application Performance

Each pane in the Cloud onRamp dashboard displays the performance of a cloud application.

Each application pane displays the number of vEdge routers accessing the application and the quality of the connection:

- The bottom status bar displays green for devices experiencing good quality.
- The middle status bar displays yellow for devices experiencing average quality.
- The top status bar displays red for devices experiencing bad quality.

The number to the right of each status bar indicates how many devices are experiencing that quality of connection.


### View Details about an Application

1. Click in an application's pane. vManage NMS displays a list of sites accessing the application.
2. Click a graph icon in the vQoE Score column to display vQoE history for that site.
  - Click the time duration links to adjust the data the chart displays.
  - Hover over a point on the chart to display vQoE details for that point in time.

## Manage Cloud onRamp Applications

Select Manage Cloud onRamp ► Applications. The screen changes and displays the following elements:

- Add Applications and VPN—Add applications to Cloud onRamp service.
- Applications table—Display applications and VPNs configured for Cloud onRamp service.



To edit the VPN configured for an application, click the Edit icon for that application, then enter the new VPN. You can enter any VPN other than 0, which is the transport VPN, or 512, which is the management VPN.

To add applications to Cloud onRamp service:

1. From the Manage Cloud onRamp drop-down, located to the right of the title bar, select Applications.
2. Click the Add Applications and VPN button. The Add Applications & VPN popup window displays.
3. In the Applications field, select an application.
4. In the VPN field, enter the service VPN in which that application runs. You can enter any VPN other than 0 and 512.
5. Click Add.
6. Repeat Steps 2 through 4 for each application you want to add.
7. Click Save Changes.


## Manage Cloud onRamp Client Sites

Client sites in Cloud onRamp service choose the best gateway site for each application to use for accessing the internet.

## Configuration

In the title bar, select Manage Cloud onRamp ► Client Sites. The screen changes and displays the following elements:

- Attach Sites—Add client sites to Cloud onRamp service.
- Detach Sites—Remove client sites from Cloud onRamp service.
- Client sites table—Display client sites configured for Cloud onRamp service.



To display details about a client site, select the site from the Client Sites Table and click the forward arrow located to the right of the row.

To detach a client site, select the site from the Client Sites Table and click Detach Sites.

To add client sites to Cloud onRamp service:

1. Click Attach Sites. The Attach Sites popup window displays all sites in your overlay network, with available sites highlighted. For a site to be available, all devices at that site must be running in vManage mode.
2. In the Available Sites pane, select a site to attach and click the right arrow. If you wish to remove a site from the Selected Sites pane, select the site and click the left arrow.
3. Click Attach to push the new template to the vEdge routers.

## Manage Cloud onRamp Gateways


Gateway sites in Cloud onRamp service choose the best network path for application traffic that originates at client sites.

In the title bar, select Manage Cloud onRamp ► Gateways. The screen changes and displays the following elements:

- Attach Gateways—Attach gateway sites.
- Detach Sites—Remove gateway sites from Cloud onRamp service.

## Configuration

- Edit Sites—Edit interfaces on gateway sites.
- Gateways table—Display gateway sites configured for Cloud onRamp service.



To display details about a gateway site, select the site from the Gateways Table and click the forward arrow located to the right of the row.

To detach a gateway site, select the site from the Gateways Table and click Detach Gateways.

To attach gateways:

1. Click Attach Gateways. The Attach Gateways screen displays. The Site List shows all available sites in your overlay network. For a site to be available, all devices at that site must be running in vManage mode.
2. In the Available Gateways pane, select a site to attach and click the right arrow. If you wish to remove a site from the Selected Sites pane, select the site and click the left arrow.
3. If you would like to specify GRE interfaces for Cloud onRamp service to use:
  - a. Click Add Interfaces to Selected Sites.
  - b. In the Interfaces drop-downs, add GRE interfaces.

If you do not specify interfaces for Cloud onRamp service to use, the system will select a NAT-enabled physical interface from VPN 0.

4. Click Attach to push the new template to the vEdge routers.

To edit Cloud onRamp interfaces on gateway sites:

1. Select the sites you want to edit and click Edit Gateways.
2. In the Edit Interfaces of Selected Sites screen, select a site to edit.



## Configuration


- To add interfaces, click the Interfaces field to select available interfaces.
  - To remove an interface, click the X beside its name.
3. Click Save Changes to push the new template to the vEdge routers.

## Manage Cloud onRamp DIA Sites

In Cloud onRamp service, DIA sites choose the best internet path for the application to use. They also consider paths that exit to the internet through gateway sites.

In the title bar, select Manage Cloud onRamp ► DIA. The screen changes and displays the following elements:

- Attach DIA Sites—Attach DIA sites.
- Detach DIA Sites—Remove DIA sites.
- Edit DIA Sites—Edit interfaces on DIA sites.
- Sites table—Display sites configured for Cloud onRamp service.



To display details about a site, select the site from the Sites Table and click the forward arrow located to the right of the row.

To detach a DIA site, select the site from the Sites Table and click Detach DIA Sites.

To attach DIA sites:

1. Click Attach DIA Sites. The Attach DIA Sites screen displays. The Site List shows all sites in your overlay network, with available sites highlighted. For a site to be available, all devices at that site must be running in vManage mode.
2. In the Available Sites pane, select a site to attach and click the right arrow. If you wish to remove a site from the Selected Sites pane, select the site and click the left arrow.

3. If you would like to specify GRE interfaces for Cloud onRamp service to use:

- a. Click Add Interfaces to Selected Sites.
- b. In the Interfaces drop-downs, add GRE interfaces.

If you do not specify interfaces for Cloud onRamp service to use, the system will select a NAT-enabled physical interface from VPN 0.

4. Click Save Changes to push the new template to the vEdge routers.

To edit Cloud onRamp interfaces on DIA sites:

1. Select the sites you want to edit and click Edit DIA Sites.
2. In the Edit Interfaces of Selected Sites screen, select a site to edit.
  - To add interfaces, click the Interfaces field to select available interfaces.
  - To remove an interface, click the X beside its name.
3. Click Save Changes to push the new template to the vEdge routers.


## Cloud OnRamp with AWS

Use the Cloud OnRamp screen to create virtual private cloud (VPC) instances for hosting vEdge Cloud routers in different AWS regions in the public internet. A Cloud OnRamp setup comprises three components:

- A transit VPC, which connects a Viptela overlay network to one or more cloud-based applications.
- A host VPC, which is where cloud-based applications reside.
- The connections, or mappings, between the transit VPC and one or more host VPCs.

## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Cloud OnRamp.
- Add New Cloud Instance—Click to create a Cloud OnRamp VPC instance using the cloud instance configuration wizard.
- Cloud OnRamp Dashboard—Displays after you add at least one region in an Account.
  - VPC panes—Located on the Cloud OnRamp Dashboard, directly under the Add New Cloud Instance button, is a pane for each region corresponding to an account that has been created. Each pane shows:
    - Account number or account name used for logging in to AWS
    - Number of up and down IPsec connections for mapped host VPCs
    - Number of up and down control connections for vEdge router instances within the transit VPCs



## Create a Cloud Instance

1. Click Add New Cloud Instance.
2. In the Add Cloud Instance—Log In to a Cloud Server popup:
  - a. In the Cloud drop-down, select the cloud type to be AWS.
  - b. Click IAM Role or Key to log in to the cloud server. It is recommended that you use IAM Role.
  - c. If you select IAM Role:
    - i. In the Role ARN field, enter the role ARN of the IAM role.
    - ii. In the External ID field, enter external ID created for the role ARN. It is recommended that the external ID include 10 to 20 characters in random order.  
To authenticate to the vManage NMS using an IAM role, vManage NMS must be hosted by Viptela on AWS and have the following attributes:
      - Trusts the AWS account, 200235630647, that hosts the vManage NMS.
      - Have all permissions for EC2 and VPC resources.
      - A default timeout of at least one hour.
 If vManage NMS is not hosted by Viptela on AWS, assign an IAM role with permissions to AssumeRole to the vManage server running the Cloud OnRamp process. Refer to the AWS documentation for details.
  - d. If you select Key:
    - i. In the API Key field, enter your Amazon API key.
    - ii. In the Secret Key field, enter the password associated with the API key.
3. Click Login to log in to the cloud server.  
The cloud instance configuration wizard opens. This wizard consists of three screens that you use to select a region and discover hosts VPCs, add transit VPC, and map host VPCs to transit VPCs.  
A graphic on the right side of each wizard screen illustrates the steps in the cloud instance configuration process. Steps not yet

completed are shown in light gray. The current step is highlighted within a blue box. Completed steps are indicated with a green checkmark and are shown in light orange.

4. Select a region and discover host VPCs:
  - a. In the Choose Region drop-down, select a geographical region.
  - b. Click Discover Host VPCs. A list of host VPCs discovered in that region is displayed.
  - c. Select the desired VPCs.
  - d. Click Next.
5. Add a transit VPC:
  - a. In the Transit VPC Name field, type a name for the transit VPC. The name can be up to 128 characters and can contain only uppercase and lowercase letters, the digits 0 through 9, hyphens (-), and underscores (\_). It cannot contain spaces or any other characters.
  - b. Under Device Information, enter information about the transit VPC:
    - i. In the vEdge Version drop-down, select the Viptela software version to run on the VPC transit.
    - ii. In the Size of Transit vEdge drop-down, select how much memory and how many CPUs to create on the VPC transit.
    - iii. In the Device 1 drop-down, select the serial number to use.
    - iv. In the Device 2 drop-down, select the serial number to use.
    - v. Click Advanced if you wish to enter more specific configuration options:
      1. In the Transit VPC Subnet field, enter a custom CIDR that has a network mask in the range of 16 to 25. If you choose to leave this field empty, the Transit VPC is created with a default CIDR of 10.0.0.0/16.
      2. In the SSH PEM Key drop-down, select a PEM key pair to log in to an instance. Note that the key pairs are region-specific. Refer to the AWS documentation for instructions on creating key pairs.
      3. Click Save and Finish to create the transit VPC. Or click Proceed to Mapping to continue with the wizard.
  - c. Click Next.
6. Map the host VPCs to transit VPCs:
  - a. In the table of host VPCs, select the desired host VPCs.
  - b. Click Map VPCs. The Map Host VPCs popup opens.
  - c. In the Transit VPC drop-down, select the transit VPC to map to the host VPCs.
  - d. In the VPN drop-down, select the VPN in the overlay network in which to place the mapping.
  - e. Click Map VPCs.
  - f. Click Save and Complete.

## Display Host VPCs

1. In the Cloud OnRamp Dashboard, click the pane for the desired VPC. The Host VPCs/Transit VPCs screen opens, and Host VPCs is selected by default. In the bar below this, Mapped Host VPCs is selected by default, and the table on the screen lists the mapping between host and transit VPCs, the state of the transit VPC, and the VPN ID.

## Configuration

2. To list unmapped host VPCs, click Unmapped Host VPCs. Then click Discover Host VPCs.
3. To display the transit VPCs, click Transit VPCs.

### Map Host VPCs to a Transit VPC

1. In the Cloud OnRamp Dashboard, click the pane for the desired VPC. The Host VPCs/Transit VPCs screen opens.
2. Click Unmapped Host VPCs.
3. Click Discover Host VPCs.
4. From the list of discovered host VPCs, select the desired host VPCs
5. Click Map VPCs. The Map Host VPCs popup opens.
6. In the Transit VPC drop-down, select the desired transit VPC.
7. In the VPN drop-down, select the VPN in the overlay network in which to place the mapping.
8. Click Map VPCs.

### Unmap Host VPCs

1. In the Cloud OnRamp Dashboard, click the pane for the desired VPC. The Host VPCs/Transit VPCs screen opens.
2. Click Mapped Host VPCs.
3. From the list of VPCs, select the desired host VPCs.
4. Click Unmap VPCs.
5. Click OK to confirm the unmapping.

Unmapping host VPCs deletes all VPN connections to the VPN gateway in the host VPC, and then deletes the VPN gateway. When you make additional VPN connections to a mapped host VPC, they will be terminated as part of the unmapping process.

### Display Transit VPCs

1. In the Cloud OnRamp Dashboard, click the pane for the desired VPC. The Host VPCs/Transit VPCs screen opens, and Host VPCs is selected by default.
2. Click Transit VPCs.

The table at the bottom of the screen lists the transit VPCs.

### Add a Transit VPC

1. In the Cloud OnRamp Dashboard, click the pane for the desired VPC. The Host VPCs/Transit VPCs screen opens, and Host VPCs is selected by default.
2. Click Transit VPCs.
3. Click Add Transit VPC.

## Delete a Transit VPC

1. In the Cloud OnRamp Dashboard, click the pane for the desired VPC. The Host VPCs/Transit VPCs screen opens, and Host VPCs is selected by default.
2. Click Mapped Host VPCs.
3. Select the desired host VPC, and click Unmap VPCs.
4. Click OK to confirm the unmapping.
5. Click Transit VPCs.
6. Click the Trash icon to the left of the row for the transit VPC.
7. Click OK to confirm.

## Additional Information

[Cloud OnRamp with Azure](#)

### Configuring Cloud OnRamp Service


## Cloud OnRamp with Azure

Use the Cloud OnRamp screen to create transit virtual networks (VNETs) for hosting vEdge Cloud router instances in different Azure locations in the public internet. A Cloud OnRamp setup comprises three components:

- A transit VNet, which connects a Viptela overlay network to one or more cloud-based applications.
- A host VNet, which is where cloud-based applications reside.
- The connections, or mappings, between the transit VNet and one or more host VNETs.


## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Cloud OnRamp.
- Add New Cloud Instance—Click to create a Cloud OnRamp VNet instance using the cloud instance configuration wizard.
- Cloud OnRamp Dashboard—Displays after you add at least one cloud instance.
  - VNet panes—Located on the Cloud OnRamp Dashboard, directly under the Add New Cloud Instance button, is a pane for each VNet that has been created. For each VNet, the pane shows:
    - Credential value for the VNet
    - Name of the VNet
    - Type of VNet
    - Number of up and down connections for mapped host VNETs
    - Number of up and down connections for transit VNETs



## Create a Cloud Instance

1. Click Add New Cloud Instance:




2. In the Add Cloud Instance—Log In to a Cloud Server popup:
  - a. In the Cloud drop-down, select the cloud type to be Azure.
  - b. To give vManage programmatic access to your Azure Subscription, log in to the cloud server:
    - i. In the Subscription ID field, enter the ID of the Azure subscription you want to use as part of the Cloud onRamp workflow.
    - ii. In the Client ID field, enter the ID of an existing application or create a new application in Azure. To create a new application, go to your Azure Active Directory ► App Registrations ► New Application Registration.
    - iii. In the Tenant ID field, enter the ID of your Azure account. To find the tenant ID, go to your Azure Active Directory and click Properties.
    - iv. In the Secret Key field, enter the password associated with the client ID.
3. Click Log In.
 

The cloud instance configuration wizard opens. This wizard consists of three screens that you use to select a location and discover host VNets, add transit VNet, and map host VNets to transit VNets.

A graphic on the right side of each wizard screen illustrates the steps in the cloud instance configuration process. Steps not yet completed are shown in light gray. The current step is highlighted within a blue box. Completed steps are indicated with a green checkmark and are shown in light orange.





4. Select a location and discover host VNets:
  - a. In the Choose Location drop-down, select a geographical location.
  - b. Click Discover Host VNets. A list of host VNets discovered in that location is displayed.
  - c. Select the desired VNet.
  - d. Click Next.
5. Add a transit VNet:
  - a. In the Transit VNet Name field, type a name for the transit VNet. The name can be up to 32 characters and can contain only uppercase and lowercase letters, the digits 0 through 9, hyphens (–), and underscores (\_). It cannot contain spaces or any other characters.
  - b. Under Device Information, enter information about the transit VNet:
    - i. In the WAN Edge Version drop-down, select the Viptela software version to run on the VNet transit. The drop-down lists the published versions of the Viptela software in the Azure marketplace.
    - ii. In the Size of Transit VNet drop-down, select how much memory and how many CPUs to create on the VNet transit.
    - iii. In the Device 1 drop-down, select the serial number to use.
    - iv. In the Device 2 drop-down, select the serial number to use.
    - v. Click Advanced if you wish to enter more specific configuration options.
    - vi. In the Transit VPC Subnet field, enter a custom CIDR that has a network mask in the range of 16 to 25. If you choose to leave this field empty, the Transit VPC is created with a default CIDR of 10.0.0.0/16.

- c. Click Next.
6. Map the host VNets to transit VNets:
  - a. In the table of host VNets, select the desired host VNet.
  - b. Click Map VNets. The Map Host VNets popup opens.
  - c. In the Transit VNet drop-down, select the transit VNet to map to the host VNets.
  - d. In the VPN drop-down, select the VPN in the overlay network in which to place the mapping.
  - e. In the IPSec Tunnel CIDR section, enter two pairs of interface IP addresses for each vEdge Cloud router to configure IPSec tunnels to reach the Azure virtual network transit. The IP addresses must be network addresses in the /30 subnet, be unique across the overlay network, and not be a part of the host VNet CIDR. If they are part of the host VNet CIDR, Azure will return an error while attempting to create VPN connections to the transit VNet.
  - f. In the Azure Information section:
    - i. In the BGP ASN field, enter the ASN that will be configured on the Azure Virtual Network Transit that is spun up within the host VNet. Use an ASN that is not part of an existing configuration on Azure. For acceptable ASN values, refer to Azure documentation.
    - ii. In the Host VNet Gateway Subnet field, enter a host VNet subnet in which the Virtual Network Gateway can reside. It is recommended you use a /28 subnet or higher. You must not provide a subnet that is already created in the VNet.
  - g. Click Map VNets.
  - h. Click Save and Complete.

When you configure the two vEdge Cloud routers that form the transit VNet, ensure that the color you assign to the tunnel interface in the VPN feature configuration template for VPN 0, is a public color, not a private color. Public colors are **3g**, **biz-internet**, **blue**, **bronze**, **custom1**, **custom2**, **custom3**, **default**, **gold**, **green**, **lte**, **metro-ethernet**, **mpls**, **public-internet**, **red**, and **silver**.

## Display Host VNets

1. In the Cloud OnRamp Dashboard, click the pane for the desired VNet. The Host VNets/Transit VNets screen opens, and Host VNets is selected by default. In the bar below this, Mapped Host VNets is selected by default, and the table on the screen lists the mapping between host and transit VNets, the state of the transit VNet, and the VPN ID.
2. To list unmapped host VNets, click Unmapped Host VNets.
3. To display the transit VNets, click Transit VNets.

## Map Host VNets to an Existing Transit VNet

1. In the Cloud OnRamp Dashboard, click the pane for the desired location of the required account. The Host VNets/Transit VNets screen opens.
2. Click Unmapped Host VNets.
3. Click Discover Host VNets.
4. From the list of discovered host VNets, select the desired host VNet.
5. Click Map VNets. The Map Host VNets popup opens.
6. In the Transit VNet drop-down, select the desired transit VNet.

## Configuration

7. In the VPN drop-down, select the VPN in the overlay network in which to place the mapping.
8. Click Map VNets.

## Unmap Host VNets

1. In the Cloud OnRamp Dashboard, click the pane for the desired VNet. The Host VNets/Transit VNets screen opens.
2. Click Mapped Host VNets.
3. From the list of VNets, select the desired host VNets. It is recommended that you unmap one vNet at a time. If you want to unmap multiple vNets, do not select more than three in a single unmapping operation.
4. Click Unmap VNets.
5. Click OK to confirm the unmapping.

## Display Transit VNets

1. In the Cloud OnRamp Dashboard, click the pane for the desired VNets. The Host VNets/Transit VNets screen opens, and Host VNets is selected by default.
2. Click Transit VNets.

The table at the bottom of the screen lists the transit VNets.

## Add a Transit VNet

1. In the Cloud OnRamp Dashboard, click the pane for the desired VNet. The Host VNets/Transit VNets screen opens, and Host VNets is selected by default.
2. Click Transit VNets.
3. Click Add Transit VNet.

## Delete a Transit VNet

1. In the Cloud OnRamp Dashboard, click the pane for the desired VNet. The Host VNets/Transit VNets screen opens, and Host VNets is selected by default.
2. Click Mapped Host VNets.
3. Select the desired host VNet, and click Unmap VNets.
4. Click OK to confirm the unmapping.
5. Click Transit VNets.
6. Click the Trash icon to the left of the row for the transit VNet.
7. Click OK to confirm.

## Additional Information

[Cloud OnRamp with AWS](#)


### Configuring Cloud OnRamp Service

## Devices

Use the Devices screen to add or delete WAN Edge routers and controller devices from the overlay network. WAN Edge routers are vEdge and other WAN routers. Controller devices are the vManage NMS, the vSmart controller, and the vBond orchestrator.

## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Devices.
- WAN Edge List tab—Upload the WAN Edge authorized serial number file to the vManage NMS. When you first open the Devices screen, the WAN Edge List tab is selected.
  - Change mode—Switch between vManage and CLI mode.
  - Upload WAN Edge List—Upload the WAN edge router authorized serial number file to the vManage NMS.
  - Export Bootstrap Configuration—Generate and download a bootstrap configuration for multiple vEdge Cloud routers.
  - Sync Smart Account—Download the updated device list to vManage NMS and send it to the vBond orchestrator.
  - Table of routers in the overlay network—To re-arrange the columns, drag the column title to the desired position.
- Controllers tab—Add controllers to the overlay network.
  - Add Controller drop-down—Add controllers to the overlay network.
  - Change mode drop-down—Switch between vManage and CLI mode.
  - Table of controller devices in the overlay network—To re-arrange the columns, drag the column title to the desired position.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Refresh icon—Click to refresh data in the device table with the most current data.
- Export icon—Click to download all data to a file, in CSV format.
- Show Table Fields icon—Click to display or hide columns from the device table. By default, all columns are displayed.



## Change Configuration Modes

To toggle a router from vManage mode to CLI mode:

1. In WAN Edge List tab, select a device.
2. Click the Change Mode drop-down and select CLI mode.

An SSH window opens. To log in to the device, enter a username and password. You can then issue CLI commands to configure or monitor the device.

To toggle a controller device from vManage mode to CLI mode:

1. In the Controllers tab, select a device.
2. Click the Change Mode drop-down.
3. Select CLI mode and then select the device type. The Change Mode CLI window opens.
4. From the vManage mode pane, select the device and click the right arrow to move the device to the CLI mode pane.
5. Click Update to CLI Mode.

An SSH window opens. To log in to the device, enter a username and password. You can then issue CLI commands to configure or monitor the device.

## Upload WAN Edge Router Authorized Serial Number File

The WAN Edge router authorized serial number file contains the chassis and serial numbers of all valid vEdge routers in the overlay network. You receive this file from Viptela. Then, from the vManage NMS, you send it to the controllers in the network. This file is required to allow the Viptela overlay network components to validate and authenticate each other and thus to allow the overlay network to become operational.

To upload the WAN edge router authorized serial number file to the vManage NMS and then download it to all the controllers in the overlay network:

1. In the WAN Edge List tab, click Upload WAN Edge List.
2. In the Upload WAN Edge List window:
  - a. Click Choose File and select the WAN edge router authorized serial number file you received from Viptela.
  - b. To automatically validate the routers and send their chassis and serial numbers to the controllers, ensure that the checkbox Validate the Uploaded WAN Edge List and Send to Controllers is selected. (It is selected by default.) If you do not select this option, you must individually validate each router in Configuration ► Certificates ► WAN Edge List.
  - c. Click Upload.

A list of routers in the network is displayed in the router table, with details about each router.

## Upload WAN Edge Router Serial Numbers from Cisco Smart Account

To upload the WAN edge router authorized serial numbers from a Cisco Smart account to the vManage NMS and then download it to all the controllers in the overlay network:

1. In the WAN Edge List tab, click Sync Smart Account.
2. In the Sync Smart Account window:
  - a. Enter the username and password for your Smart account..
  - b. To automatically validate the routers and send their chassis and serial numbers to the controllers, ensure that the checkbox Validate the Uploaded WAN Edge List and Send to Controllers is selected. (It is selected by default.) If you do not select this option, you must individually validate each router in Configuration ► Certificates ► WAN Edge List.
  - c. Click Sync.

A list of routers in the network is displayed in the router table, with details about each router.

## Generate Bootstrap Configuration for a vEdge Cloud Router

For vEdge Cloud routers, you need to generate a bootstrap configuration file that you use when you create vEdge cloud VM instances.

To generate and download a bootstrap configuration for one or more vEdge Cloud routers:

1. In the WAN Edge List tab, click the Export Bootstrap Configuration button.
2. In the Export Bootstrap Configuration window, in the Bootstrap Configuration field, click Cloud-Init or Encoded String, depending the Hypervisor you are using to bring up the vEdge Cloud router.
3. Select the devices to configure from the Available Devices pane, or click Select All to select all devices.
4. Click the right arrow to move the devices to the Selected Devices pane.
5. Click Generate Configuration. The configurations are downloaded to the vManage NMS.

## Configuration

6. Provision the vEdge Cloud router instance in AWS, KVM, or ESXi with the bootstrap configuration. By default, ge0/0 is the device's tunnel interface and is a DHCP client. To use an interface other than ge0/0 as the tunnel interface or to use a static IP as the IP address, reconfigure the device through the CLI. For more information about configuring interfaces, see [Configure Network Interfaces](#).

After you provision the vEdge Cloud router instance, vManage NMS installs a certificate on the device and the device's token changes to a serial number. After the device's control connections to vManage NMS come up, any templates attached to the device are automatically pushed to the device.

## Export Device Data in CSV Format

To export data for all devices to a file in CSV format, click the Export icon. This icon, which is a downward-pointing arrow, is located to the right of the filter criteria both in the WAN Edge List and in the Controllers tab.

vManage NMS downloads all data from the device table to an Excel file in CSV format. The file is downloaded to your browser's default download location and is named viptela\_download.csv.

## View a Device's Running Configuration

To view a device's running configuration:

1. In the WAN Edge List or Controllers tab, select the device.
2. Click the More Actions icon to the right of the row and click Running Configuration.

## View a Device's Configuration

To view a device's configuration created using Configuration ► Templates:

1. In the WAN Edge List or Controllers tab, select the device.
2. Click the More Actions icon to the right of the row and click Local Configuration.

## Delete a WAN Edge Router

Deleting a router removes its serial and chassis numbers from the WAN edge router serial number list and permanently removes the router's configuration from the vManage NMS.

1. In the Configuration ► Certificates screen, mark the WAN Edge router as invalid.
2. In the Configuration ► Devices screen, in the WAN Edge List tab, select the router.
3. Click the More Actions icon to the right of the row and click Delete WAN Edge.
4. Click OK to confirm deletion of the device.
5. In the Configuration ► Certificates screen, click Send to Controller.

## Copy Router Configuration

When you are replacing one router at a site with another router, you copy the old router's configuration to the new router. Then you remove the old router from the network and add the new one.

To copy the configuration from the old router to the new router:

---

## Configuration

1. In the Configuration ► Certificates screen, mark the new vEdge router as invalid.
2. In the Configuration ► Devices screen, in the WAN Edge List tab, select the old router.
3. Click the More Actions icon to the right of the row and click Copy Configuration.
4. In the Copy Configuration window, select the new router.
5. Click Update to confirm the copy of the configuration.

After you have copied the configuration to the new router, you can add the new router to the network. First, delete the old router from the network, as described below. Then add the new router to the network:

1. In the Configuration ► Certificates screen, mark the new router as valid.
2. Click Send to Controller.

## Decommission a vEdge Cloud Router

Decommissioning a vEdge Cloud router removes the device's serial number from vManage NMS and generates a new token for the device. To do so:

1. In the WAN Edge List tab, select a vEdge Cloud router.
2. Click the More Actions icon to the right of the row and click Decommission WAN Edge.
3. Click OK to confirm the decommissioning of the router.

## View Log of Template Activities

To view a log of activities related to creation of configuration templates and the status of attaching configuration templates to devices:

1. In the WAN Edge List or Controllers tab, select the device.
2. Click the More Actions icon to the right of the row and click Template Log.

## View Status of Device Bringup

To view the status of the operations involved in bringing a router or controller up in the overlay network:

1. In the WAN Edge List or Controllers tab, select the device.
2. Click the More Actions icon to the right of the row and click Device Bring Up.

## Add a vBond Orchestrator

1. In the Controllers tab, click the Add Controller drop-down and select vBond.
2. In the Add vBond window:
  - a. Enter the management IP address of the vBond controller.
  - b. Enter the username and password to access the vBond orchestrator.
  - c. Select the Generate CSR checkbox to allow the certificate-generation process to occur automatically.



## Configuration

- d. Click Add.
3. Repeat Steps 1 and 2 to add additional vBond orchestrators.

The new vBond orchestrator is added to the list of controllers in the Controllers screen.

## Add a vSmart Controller

1. In the Controllers tab, click the Add Controller drop-down and select vSmart.
2. In the Add vSmart window:
  - a. Enter the system IP address of the vSmart controller.
  - b. Enter the username and password to access the vSmart controller.
  - c. Select the protocol to use for control-plane connections. The default is DTLS.
  - d. If you select TLS, enter the port number to use for TLS connections. The default is 23456.
  - e. Select the Generate CSR checkbox to allow the certificate-generation process to occur automatically.
  - f. Click Add.
3. Repeat Steps 1 and 2 to add additional vSmart controllers. The vManage NMS can support up to 20 vSmart controllers in the network.

The new vSmart controller is added to the list of controllers in the Controllers screen.

## Edit Controller Details

To edit the IP address and login credentials of a controller device:

1. In the Controllers tab, select the controller.
2. Click the More Actions icon to the right of the row and click Edit.
3. In the Edit window, edit the IP address and the login credentials.
4. Click Save.

## Delete a Controller

1. In the Controllers tab, select the controller.
2. Click the More Actions icon to the right of the row and click Invalidate.
3. Click OK to confirm the removal of the device and all its control connections.

## Configure Reverse Proxy on Controllers

To configure reverse proxy on an individual vManage NMS and vSmart controller device:

1. In the Controllers tab, select the device.
2. Click the More Actions icon to the right of the row, and click Add Reverse Proxy. The Add Reverse Proxy popup is displayed.
3. Click Add Reverse Proxy.

## Configuration

4. Configure the private IP address and port number for the device. The private IP address is the IP address of the transport interface in VPN 0. The default port number is 12346. This is the port used to establish the connections that handle control and traffic in the overlay network.
5. Configure the proxy IP address and port number for the device, to create the mapping between the private and public IP addresses and port numbers.
6. If the vManage NMS or vSmart controller has multiple cores, repeat Steps 4 and 5 for each core.
7. Click Add.


To enable reverse proxy in the overlay network, in vManage NMS select Administration ► [Settings](#) . Then click Edit to the right of the Reverse Proxy bar, click Enabled, and click Save.

## Policies

Use the Policies screen to create and activate centralized and localized control and data policies for vSmart controllers and vEdge routers.

## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Policies, and the following:
  - Custom Options—Click to display, create, and edit a components for use in policy. For centralized policy, the components are CLI policies, lists, topologies, and traffic policies. For localized policy, the components are CLI policies, lists, forwarding class/QoS definitions, access control lists (ACLs), and route policies.
- Centralized Policy tab—Create a centralized policy. When you first open the Policies screen, the Centralized Policy tab is selected.
  - Add Policy—Click to create a centralized policy using a policy configuration wizard.
- Localized Policy tab—Create a localized policy.
  - Add Policy—Click to create a localized policy using a policy configuration wizard.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Refresh icon—Click to refresh data in the policies table with the most current data.
- Show Table Columns icon—Click to display or hide columns from the policies table. By default, all columns are displayed.
- Policies table—To re-arrange the columns, drag the column title to the desired position.



## Configure Centralized Policy

You configure centralized policy with a configuration wizard. The wizard is a UI policy builder that consists of four screens to configure and modify the following centralized policy components:

- Groups of interest, also called lists
- Topologies and VPN membership
- Traffic rules
- Applying policies to sites and VPNs

You configure some or all these components depending on the specific policy you are creating. To skip a component, click the Next button at the bottom of the screen. To return to a component, click the Back button at the bottom of the screen.

You apply centralized policies by activating them, as described later in the article, to push the policies to all reachable vSmart controllers.

For more information about the centralized policy components, see [Configuring Centralized Control Policy](#) . For information about application-aware routing policy components, see [Configuring Application-Aware Routing](#) .

### Step 1: Start the Policy Configuration Wizard

To start the policy configuration wizard:

1. In vManage NMS, select the Configure ► Policies screen.

## Configuration

2. Select the Centralized Policy tab.
3. Click Add Policy.

The policy configuration wizard opens, and the Create Groups of Interest screen displays.

## Step 2: Configure Groups of Interest

In Create Groups of Interest, create lists of groups to use in centralized policy:

The screenshot shows the 'Create Groups of Interest' wizard in Cisco vManage. The left navigation pane has 'Policies' selected. The main content area shows a list of application groups. The list has the following data:


Name	Entries	Reference Count	Updated By	Last Updated	Action
Microsoft_Apps	bing, hockeyapp, l...	0	system	27 Mar 2018 2:32...	[Edit] [Refresh] [Delete]
Google_Apps	blogger, chrome, ...	0	system	27 Mar 2018 2:32...	[Edit] [Refresh] [Delete]
Ban_List	peer-to-peer	1	system	24 Apr 2018 9:19...	[Edit] [Refresh] [Delete]
High_priority	web, file-server, w...	0	system	24 Apr 2018 9:19...	[Edit] [Refresh] [Delete]

At the bottom of the wizard, there are 'Next' and 'CANCEL' buttons.


1. In the left pane, select the type of list to use with the localized policy. It can be one of the following:

- Application
- Color
- Data Prefix
- Policer
- Prefix
- Site
- SLA Class
- TLOC
- VPN

2. In the right pane, click the New button. The New List portion of the screen opens. For example:




3. Enter a name for the list, and enter or select the components to include in the list. For application lists, note that the Google\_Apps and Microsoft\_Apps lists are preconfigured, and you cannot edit or delete them. For example:



4. Click Add to create the new list.
5. Repeat Steps 1 through 4 to create additional lists.
6. To edit, copy, or delete an existing list, click the Edit, Copy, or Trash Bin icon in the Action column.
7. Click Next to move to Configure Topology and VPN Membership in the wizard.


### Step 3: Configure Topology and VPN Membership

When you first open the Configure Topology and VPN Membership screen, the Topology tab is selected by default:




To configure topology and VPN membership:

1. To configure a topology policy component:
  - a. In the Topology tab, click the Add Topology drop-down.
  - b. Select the desired network topology:



- c. Enter a name and description for the topology, and select the VPN list to which the topology applies.
  - d. Click the New button, and enter the information for the topology component.
  - e. Enter a name for the topology component, and enter or select the components to include in it.
  - f. Click Save.
2. To configure a VPN membership policy component:
    - a. In the VPN Membership tab, click Add VPN Membership Policy:






- b. In the Update VPN Membership Policy popup, enter a name and description of the VPN membership, and select site lists and VPN lists. To create new lists, click Add List.
  - c. Click Save.
3. To edit, copy, or delete an existing topology or VPN membership policy, select it and click the Edit, Copy, or Trash Bin icon in the Action column.
4. Click Next to move to Configure Traffic Rules in the wizard.


## Step 4: Configure Traffic Rules

When you first open the Traffic Rules screen, the Application-Aware Routing tab is selected by default:



To configure traffic rules:


1. In the Application-Aware Routing tab, select the desired policy type—Application-Aware Routing, Traffic Data, or Cflowd.
2. Click the Add Policy drop-down.
3. To import an existing policy, select Import Existing. In the Import Existing Data Policy popup, select the name of the file containing the data policy. Then click Import.
4. To create a new policy, select Create New, and in the left pane, click Sequence Type.
5. For an application-aware routing policy:
  - a. In the right pane, click Sequence Rule.
  - b. Add the match and action rules.
  - c. Add additional sequences as needed. Drag and drop sequences to re-order them.
  - d. Click Save Application-Aware Routing Policy.
6. For a traffic data policy:
  - a. From the Add Data Policy popup, select the policy type:



- b. In the right pane, click Sequence Rule.
  - c. Add the match and action rules.
  - d. Add additional sequences as needed. Drag and drop sequences to re-order them
  - e. Click Save Data Policy.
7. For cflowd policy:
    - a. To configure the cflowd template, enter values for the active flow timeout, inactive flow timeout, flow refresh interval, and sampling interval.
    - b. To configure a collector list, click Add New Collector. Enter the VPN ID where the collector is located, its IP address, port number, transport protocol, and source interface. Click Add.
    - c. Click Save Cflowd Policy.
  8. Click Next to move to Apply Policies to Sites and VPNs in the wizard.

## Step 5: Apply Policy to Sites and VPNs

In Apply Policies to Sites and VPNs, apply a policy to overlay network sites and VPNs:



1. Enter a name for the policy. This field is mandatory and can contain only uppercase and lowercase letters, the digits 0 through 9, hyphens (–), and underscores (\_). It cannot contain spaces or any other characters.
2. Enter a description of the policy. This field is mandatory, and it can contain any characters and spaces. It can contain up to 2048 characters.
3. From the Topology bar, select the tab that corresponds to the type of policy block—Topology, Application-Aware Routing, Traffic Data, or Cflowd. The table then lists policies that you have created for that type of policy block.
4. Associate the policy with VPNs and sites. The choice of VPNs and sites depends on the type of policy block:
  - a. For a Topology policy block, click Add New Site List and VPN List or Add New Site. Some topology blocks might have no Add buttons. Select one or more site lists, and select one or more VPN lists. Click Add.
  - b. For an Application-Aware Routing policy block, click Add New Site List and VPN list. Select one or more site lists, and select one or more VPN lists. Click Add.
  - c. For a Traffic Data policy block, click Add New Site List and VPN List. Select the direction for applying the policy (From Tunnel, From Service, or All), select one or more site lists, and select one or more VPN lists. Click Add.
  - d. For a cflowd policy block, click Add New Site List. Select one or more site lists, Click Add.
5. Click Preview to view the configured policy. The policy is displayed in CLI format.
6. Click Save Policy. The Configuration ► Policies screen opens, and the policies table includes the newly created policy.

## Configure Localized Policy

You configure localized policy with a configuration wizard. The wizard is a UI policy builder that consists of five screens to configure and modify the following localized policy components:

## Configuration

- Groups of interest, also called lists
- Forwarding classes to use for QoS
- Access control lists (ACLs)
- Route policies
- Policy settings

You configure some or all these components depending on the specific policy you are creating. To skip a component, click the Next button at the bottom of the screen. To return to a component, click the Back button at the bottom of the screen.

You apply localized policies to specific vEdge router interfaces. You associate a localized policy with an interface in the VPN Interface Bridge, VPN Interface Ethernet, VPN Interface GRE, VPN Interface PPP, or VPN Interface PPP Ethernet feature configuration template.

For more information about the localized policy components, see [Configuring Localized Data Policy for IPv4](#) and [Configuring Localized Data Policy for IPv6](#).

### Step 1: Start the Policy Configuration Wizard


To start the policy configuration wizard:

1. In vManage NMS, select the Configure ► Policies screen.
2. Select the Localized Policy tab.
3. Click Add Policy.


The policy configuration wizard opens, and the Create Groups of Interest screen displays.

### Step 2: Configure Groups of Interest

In the Create Groups of Interest screen, create lists to use in localized policy:




- In the left pane, select the type of list to use with the localized policy. It can be one of the following:
  - AS Path
  - Community
  - Data Prefix
  - Extended Community
  - Mirror
  - Policer
  - Prefix
- In the right pane, click the New button. The New List portion of the screen opens. For example:



3. Enter a name for the list, and enter or select the components to include in the list. For information entering AS path, community and extended community, and data prefix and prefix values, see [Configuring Localized Control Policy](#) . For information about entering mirroring and policer parameters, see [Configuring Localized Data Policy for IPv4](#) .
4. Click Add to create the new list.
5. Repeat Steps 1 through 4 to create additional lists.
6. To edit, copy, or delete an existing list, click the Edit, Copy, or Trash Bin icon in the Action column.
7. Click Next to move to Configure Forwarding Classes/QoS in the wizard. When you first open this screen, the QoS tab is selected by default.

### Step 3: Configure Forwarding Classes for QoS


When you first open the Forwarding Classes/QoS screen, the QoS tab is selected by default:



To configure forwarding classes for use by QoS:

1. To create a new QoS mapping:
  - a. In the QoS tab, click the Add QoS drop-down.
  - b. Select Create New.
  - c. Enter a name and description for the QoS mapping.
  - d. Click Add Queue. The Add Queue popup displays:






- e. Select the queue number from the Queue drop-down.
  - f. Select the maximum bandwidth and buffer percentages, and the scheduling and drop types. Enter the forwarding class.
  - g. Click Save.
2. To import an existing QoS mapping:
    - a. In the QoS tab, click the Add QoS drop-down.
    - b. Select Import Existing.
    - c. Select a QoS mapping.
    - d. Click Import.
  3. To view or copy a QoS mapping or to remove the mapping from the localized policy, click the More Actions icon to the right of the row, and select the desired action.
  4. To configure policy rewrite rules for the QoS mapping:
    - a. In the QoS tab, click the Add Rewrite Policy drop-down..
    - b. Select Create New.
    - c. Enter a name and description for the rewrite rule.
    - d. Click Add Rewrite Rule. The Add Rule popup displays.
    - e. Select a class from the Class drop-down.
    - f. Select the priority (Low or High) from the Priority drop-down.

## Configuration


- g. Enter the DSCP value (0 through 63) in the DSCP field.
  - h. Enter the class of service (CoS) value (0 through 7) in the Layer 2 Class of Service field to include an 802.1p marking in the packet.
  - i. Click Save.
5. To import an existing rewrite rule:
    - a. In the QoS tab, click the Add Rewrite Policy drop-down..
    - b. Select Import Existing.
    - c. Select a rewrite rule.
    - d. Click Import.
  6. Click Next to move to Configure Access Lists in the wizard.

## Step 4: Configure ACLs

In the Configure Access Control Lists screen, configure ACLs:



1. To create a new IPv4 ACL, click the Add Access Control List Policy drop-down. Then select Add IPv4 ACL Policy:




2. To create a new IPv6 ACL, click the Add Access Control List Policy drop-down. Then select Add IPv6 ACL Policy.
3. Enter a name and description for the ACL.
4. In the left pane, click Add ACL Sequence. An Access Control List box is displayed in the left pane.
5. Double-click the Access Control List box, and type a name for the ACL.
6. In the right pane, click Add Sequence Rule to create a single sequence in the ACL. The Match tab is selected by default.
7. Click a match condition.
8. On the left, enter the values for the match condition.
9. On the right enter the action or actions to take if the policy matches.
10. Repeat Steps 6 through 8 to add match–action pairs to the ACL.
11. To rearrange match–action pairs in the ACL, in the right pane drag them to the desired position.
12. To remove a match–action pair from the ACL, click the X in the upper right of the condition.
13. Click Save Match and Actions to save a sequence rule.
14. To rearrange sequence rules in an ACL, in the left pane drag the rules to the desired position.
15. To copy, delete, or rename an ACL sequence rule, in the left pane, click More Options next to the rule's name and select the desired option.
16. If no packets match any of the ACL sequence rules, the default action is to drop the packets. To change the default action:
  - a. Click Default Action in the left pane.

## Configuration

- b. Click the Pencil icon.
  - c. Change the default action to Accept.
  - d. Click Save Match and Actions.
17. Click Next to move to Configure Route Policy in the wizard.

## Step 5: Configure Route Policies

In Configure Route Policy, configure route policies:



1. In the Add Route Policy tab, select Create New.
2. Enter a name and description for the route policy.
3. In the left pane, click Add Sequence Type. A Route box is displayed in the left pane.
4. Double-click the Route box, and type a name for the route policy.
5. In the right pane, click Add Sequence Rule to create a single sequence in the policy. The Match tab is selected by default.
6. Click a match condition.
7. On the left, enter the values for the match condition.
8. On the right enter the action or actions to take if the policy matches.
9. Repeat Steps 6 through 8 to add match–action pairs to the route policy.

## Configuration

10. To rearrange match–action pairs in the route policy, in the right pane drag them to the desired position.
11. To remove a match–action pair from the route policy, click the X in the upper right of the condition.
12. Click Save Match and Actions to save a sequence rule.
13. To rearrange sequence rules in an route policy, in the left pane drag the rules to the desired position.
14. To copy, delete, or rename an route policy sequence rule, in the left pane, click More Options next to the rule's name and select the desired option.
15. If no packets match any of the route policy sequence rules, the default action is to drop the packets. To change the default action:
  - a. Click Default Action in the left pane.
  - b. Click the Pencil icon.
  - c. Change the default action to Accept.
  - d. Click Save Match and Actions.
16. Click Next to move to Policy Overview in the wizard.

## Step 6: Configure Policy Settings

In Policy Overview, configure policy settings:

The screenshot displays the Cisco vManage interface for configuring a localized master policy. The top navigation bar includes 'CONFIGURATION | POLICIES Localized Policy > Add Policy'. A progress bar indicates the current step is 'Policy Overview'. The main content area contains the following fields and settings:

- Policy Name:** Input field with a placeholder 'Maximum of 128 characters'.
- Policy Description:** Input field with a placeholder 'Description of the policy'.
- Policy Settings:**
  - Checkboxes for: Netflow, Application, Cloud QoS, Cloud QoS Service side, and Implicit ACL Logging.
  - Log Frequency:** Input field with a placeholder 'Enter in seconds (maximum 2147483647)'.

At the bottom of the form, there are buttons for 'BACK', 'Preview', 'Save Policy', and 'CANCEL'.

1. Enter a name and description for the route policy.

---

## Configuration

2. To enable cflowd visibility so that a vEdge router can perform traffic flow monitoring on traffic coming to the router from the LAN, click Netflow.
3. To enable application visibility so that a vEdge router can monitor and track the applications running on the LAN, click Application.
4. To enable QoS scheduling and shaping for traffic that a vEdge Cloud router receives from transport-side interfaces, click Cloud QoS.
5. To enable QoS scheduling and shaping for traffic that a vEdge Cloud router receives from service-side interfaces, click Cloud QoS Service Side.
6. To log the headers of all packets that are dropped because they do not match a service configured by an Allow Service parameter on a tunnel interface, click Implicit ACL Logging.
7. To configure how often packets flows are logged, click Log Frequency. Packet flows are those that match an access list (ACL), a cflowd flow, or an application-aware routing flow.
8. Click Preview to view the full policy in CLI format.
9. Click Save Policy.

## View a Policy

1. In the Centralized Policy or Localized Policy tab, select a policy.
2. Click the More Actions icon to the right of the column and click View. Policies created with the UI policy builder are displayed in graphical format. Policies created using the CLI are displayed in text format.
3. Click Cancel to return to the policies table.

For a policy created using the vManage policy configuration wizard, you can view the policy in text format:

1. In the Centralized Policy or Localized Policy tab, select a policy.
2. Click the More Actions icon to the right of the column and click Preview.
3. Click Cancel to return to the policies table.

## Copy a Policy

1. In the Centralized Policy or Localized Policy tab, select a policy.
2. Click the More Actions icon to the right of the column and click Copy.
3. In the Policy Copy popup window, enter the policy name and a description of the policy.
4. Click Copy.

## Edit a Policy

For policies created using the vManage policy configuration wizard:

1. In the Centralized Policy or Localized Policy tab, select a policy.
2. Click the More Actions icon to the right of the column and click Edit.
3. Edit the policy as needed.

---

## Configuration

4. Click Save Policy Changes.

For polices created using the CLI:

1. In the Custom Options drop-down, click CLI Policy.
2. Click the More Actions icon to the right of the column and click Edit.
3. Edit the policy as needed.
4. Click Update.

## Edit or Create a Policy Component

You can create individual policy components directly and then use them or import them when you are using the policy configuration wizard:

1. In the Title bar,click the Custom Options drop-down.
2. For centralized policy, select the policy component type:
  - CLI policy—Create the policy using the command-line interface rather than the policy configuration wizard.
  - Lists—Create groups of interest to import in the Group of Interest screen in the policy configuration wizard.
  - Topology—Create a hub-and-spoke, mesh, or custom topology or a VPN membership to import in the Topology screen in the policy configuration wizard.
  - Traffic Policy—Create an application-aware routing, traffic data, or cflowd policy to import in the Traffic Rules screen in the policy configuration wizard.
3. For localized policy, select the policy component type:
  - CLI policy—Create the policy using the command-line interface rather than the policy configuration wizard.
  - Lists—Create groups of interest to import in the Group of Interest screen in the policy configuration wizard.
  - Forwarding Class/QoS—Create QoS mappings and rewrite rules to import in the Forwarding Classes/QoS screen in the policy configuration wizard.
  - Access Control Lists—Create ACLs of interest to import in the Configure Access Lists screen in the policy configuration wizard.
  - Route Policy—Create route policies to import in the Configure Route Policies screen in the policy configuration wizard.

## Delete a Policy

1. In the Centralized Policy or Localized Policy tab, select a policy.
2. Click the More Actions icon to the right of the column and click Delete.
3. Click OK to confirm deletion of the policy.

## Activate a Centralized Policy on vSmart Controllers

1. In the Centralized Policy tab, select a policy.
2. Click the More Actions icon to the right of the column and click Activate.

3. In the Activate Policy popup, click Activate to push the policy to all reachable vSmart controllers in the network.
4. Click OK to confirm activation of the policy on all vSmart controllers.

## Deactivate a Centralized Policy on vSmart Controllers

1. In the Centralized Policy tab, select a policy.
2. Click the More Actions icon to the right of the column and click Deactivate.
3. In the Deactivate Policy popup, click Deactivate to confirm that you want to remove the policy from all reachable vSmart controllers.

## Additional Information

[Application-Aware Routing](#)  
[Centralized Control Policy](#)  
[Centralized Data Policy](#)  
[Configure Policies](#)  
[Localized Control Policy](#)  
[Localized Data Policy](#)


## Security

Use the Security screen to create and activate zone-based firewalls vEdge routers.

## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Security, and the following:
  - Custom Options—Click to display, create, and edit a components for use in zone-based firewalls
- Add Policy—Click to create a zone-based firewall using a policy configuration wizard.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Refresh icon—Click to refresh data in the policies table with the most current data.
- Show Table Columns icon—Click to display or hide columns from the policies table. By default, all columns are displayed.
- Zone-based firewalls table—To re-arrange the columns, drag the column title to the desired position.





## Configure Zone-Based Firewalls

You configure zone-based firewalls with a configuration wizard. The wizard is a UI policy builder that consists of three screens to configure and modify the following zone-based firewall components:

- Groups of interest, also called lists
- Zone-based firewall match and action policy conditions
- Applying firewalls to zones

You must configure all these components depending to create a zone-based firewall. If you are modifying an existing firewall, you can skip a component by clicking the Next button at the bottom of the screen. To return to a component, click the Back button at the bottom of the screen.


For more information about zone-based firewall components, see [Configuring Zone-Based Firewalls](#).

To start the policy configuration wizard, click Add Policy. The Create Groups of Interest screen displays.


## Configure Groups of Interest

To Create Groups of Interest:

1. Click Add Policy to start the policy configuration wizard. The Create Groups of Interest screen displays:



2. In the left pane, select the type of list to use with the zone-based policy. It can be one of the following:
  - Data Prefix
  - Zones
3. In the right pane, click the New button. The New List portion of the screen displays:




4. Enter a name for the list, and enter or select the components to include in the list.
5. Click Add to create the new list.
6. Repeat Steps 2 through 5 to create additional lists.
7. To edit, copy, or delete an existing list, click the Edit, Copy, or Trash Bin icon in the Action column.
8. Click Next to move to Zone-Based Firewall in the wizard.


## Configure Zone-Based Firewall Policy

To configure the sequences of match and action policy conditions for zone-based firewalls:

1. Start the policy configuration wizard. The Create Groups of Interest screen is displayed.
2. Click Next. The Zone-Based Firewall screen is displayed:



3. Click Add Configuration.
4. To import an existing set of policy sequences, select Import Existing. In the Import Existing Zone-Based Firewall Policy popup, select the name of the file containing the policy. Then click Import.
5. To create a new policy, select Create New.
6. In the left pane, click Add Sequence:




7. Click Add Sequence Rule.
8. Add the match and action conditions.
9. Add additional sequences as needed. Drag and drop sequences to re-order them
10. Click Save Zone-Based Policy.
11. Click Next to move to Apply Configuration in the wizard.

### Apply Zone-Based Firewall Policy to a Zone Pair

In the Apply Configuration screen:

1. Start the policy configuration wizard. The Create Groups of Interest screen is displayed.
2. Click Next. The Zone-Based Firewall screen is displayed.
3. Click Next. The Apply Configuration screen is displayed:



4. Enter a name for the policy. This field is mandatory and can contain only uppercase and lowercase letters, the digits 0 through 9, hyphens (-), and underscores (\_). It cannot contain spaces or any other characters.
5. Enter a description of the policy. This field is mandatory, and it can contain any characters and spaces. It can contain up to 2048 characters.
6. Locate the desired zone-based firewall policy.
7. Click Add Zone Pair.
8. In the Source Zone drop-down, select the zone from which data traffic originates.
9. In the Destination Zone drop-down, select the zone to which data traffic is sent.
10. Click Add.
11. To edit or delete a zone pair, click the Edit or Trash Bin icon in the Action column.
12. Click Preview to view the configured policy. The policy is displayed in CLI format.
13. Click Save Policy. The Configuration ► Security screen is then displayed, and the zone-based firewalls table includes the newly created policy.

### Apply a Zone-Base Firewall to a vEdge Router

1. In vManage NMS, select the Configuration ► Templates screen.
2. If you are creating a new device template:

---

## Configuration

- a. In the Device tab, click Create Template.
  - b. From the Create Template drop-down, select From Feature Template.
  - c. From the Device Model drop-down, select one of the vEdge devices.
  - d. In the Template Name field, enter a name for the device template. This field is mandatory and can contain only uppercase and lowercase letters, the digits 0 through 9, hyphens (-), and underscores (\_). It cannot contain spaces or any other characters.
  - e. In the Description field, enter a description for the device template. This field is mandatory, and it can contain any characters and spaces.
  - f. Continue with Step 4.
3. If you are editing an existing device template:
    - a. In the Device tab, click the More Actions icon to the right of the desired template, and click the pencil icon.
    - b. Click the Additional Templates tab. The screen scrolls to the Additional Templates section.
    - c. From the Policy drop-down, select the name of a policy that you have configured.
  4. Click the Additional Templates tab located directly beneath the Description field. The screen scrolls to the Additional Templates section.
  5. From the Security Policy drop-down, select the name of the zone-based firewall you configured in the above procedure.
  6. Click Create (for a new template) or Update (for an existing template).

## View a Zone-Based Firewall

1. In the zone-based firewalls table, locate the desired policy
2. Click the More Actions icon to the right of the column and click View. Policies created with the UI policy builder are displayed in graphical format. Policies created using the CLI are displayed in text format.
3. Click Cancel to return to the zone-based firewalls table.

For a policy created using the vManage policy configuration wizard, you can view the policy in CLI format:

1. In the zone-based firewalls table, locate the desired policy.
2. Click the More Actions icon to the right of the column, and click Preview.
3. Click OK to return to the zone-based firewalls table.

## Edit a Policy

1. In the zone-based firewalls table, locate the desired policy.
2. Click the More Actions icon to the right of the column and click Edit.
3. Edit the policy as needed.
4. Click Save Policy Changes.

## Edit or Create a Zone-Based Firewall Component

You can create individual zone-based firewall components directly and then use them or import them when you are using the policy configuration wizard:

1. In the Title bar, click the Custom Options drop-down.
2. Select the policy component type:
  - Lists—Create groups of interest to import in the Group of Interest screen in the policy configuration wizard.
  - Zone-Based Firewall—Create a policy sequence to import in the Zone-Based Policy screen in the policy configuration wizard.

## Delete a Policy

1. In the zone-based firewalls table, locate the desired policy.
2. Click the More Actions icon to the right of the column and click Delete.
3. Click OK to confirm deletion of the policy.

## Additional Information

[Configure Policies](#)

[Localized Data Policy](#)

[Zone-Based Firewalls](#)

## Templates

Use the Templates screen to configure all Viptela devices in the overlay network that are managed by the vManage NMS. To do so:

1. [Create a device template](#) .
2. [Attach Viptela devices to the device template](#) .

Note: To create and modify a device's configuration, use vManage templates, along with other configuration-related screens in the vManage Configuration and Administration menus. Do not modify configurations from the command-line interface (CLI) unless you are explicitly directed to do so.

## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Templates.
- Device tab—Create device templates for configuring Viptela devices.
  - Create Template drop-down—Click to create device templates from feature template or the CLI.
  - Device template table—Table of all device templates. To re-arrange the columns, drag the column title to the desired position.
- Feature tab—Create feature templates for configuring software features that you can enable on a Viptela device.
  - Add Template button—Click to create feature templates.



## Configuration

- Feature template table—Table of all feature templates. To re-arrange the columns, drag the column title to the desired position.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Refresh icon—Click to refresh data in the templates table with the most current data.
- Show Table Columns icon—Click to display or hide columns from the templates table. By default, all columns are displayed.
- Templates table—To re-arrange the columns, drag the column title to the desired position.

The screenshot displays the Cisco vManage interface for managing templates. The main content area is titled 'CONFIGURATION | TEMPLATES' and has tabs for 'Device' and 'Feature'. A 'Create Template' button is located at the top left of the table area. A search box with a 'Search Options' dropdown is positioned above the table. The table itself has the following data:

Name	Description	Type	Device Model	Feature Templates	Devices Attached	
vm10	vm10	CLI	vSmart	0	1	...
vm9	vm9	CLI	vSmart	0	1	...
Updated_device_specific_vm6_template	device_template_test	Feature	vEdge Cloud	21	0	...
Updated_device_specific_vm5_template	device_template_test	Feature	vEdge Cloud	19	0	...

The left sidebar shows the navigation menu with 'Configuration' selected. The top right of the page has links for 'CloudExpress', 'Tasks', 'Alarms', 'Help', and 'User Profile'.

## Create a Device Template

Device templates define a device's complete operational configuration. A device template consists of a number of feature templates. Each feature template defines the configuration for a particular Cisco SD-WAN software feature. Some feature templates are mandatory, indicated with an asterisk (\*), and some are optional. Each mandatory feature template, and some of the optional ones too, have a factory-default template. For software features that have a factory-default template, you can use either the factory-default template (named `Factory_Default_feature-name_Template`) or you can create a custom feature template.

## Create a Device Template from Feature Templates

To create a device template:

1. In the Device tab, click the Create Template drop-down and select From Feature Template.

## Configuration

2. From the Device Model drop-down, select the type of device for which you are creating the template. vManage NMS displays all the feature templates for that device type. The required feature templates are indicated with an asterisk (\*), and the remaining templates are optional. The factory-default template for each feature is selected by default.
3. In the Template Name field, enter a name for the device template. This field is mandatory and can contain only uppercase and lowercase letters, the digits 0 through 9, hyphens (-), and underscores (\_). It cannot contain spaces or any other characters.
4. In the Description field, enter a description for the device template. This field is mandatory, and it can contain any characters and spaces.
5. To view the factory-default configuration for a feature template, select the desired feature template and click View Template. Click Cancel to return to the Configuration Template screen.
6. To create a custom template for a feature, select the desired factory-default feature template and click Create Template. The template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining feature parameters.
7. In the Template Name field, enter a name for the feature template. This field is mandatory and can contain only uppercase and lowercase letters, the digits 0 through 9, hyphens (-), and underscores (\_). It cannot contain spaces or any other characters.
8. In the Description field, enter a description for the feature template. This field is mandatory, and it can contain any characters and spaces.
9. For each field, enter the desired value. You may need to click a tab or the plus sign (+) to display additional fields.
10. When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <a href="#">attach a Viptela device to a device template</a> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Use Variable Values in Configuration Templates</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

12. For some groups of parameters, you can mark the entire group as device-specific. To do this, click the Mark as Optional Row box. These parameters are then grayed out so that you cannot enter a value for them in the feature template. You enter the value or values when you attach a Viptela device to a device template.
13. Click Save.
14. Repeat Steps 7 through 13 to create a custom template for each additional software feature. For details on creating specific feature templates, see the templates listed in [Available Feature Templates](#).
15. Click Create. The new configuration template is displayed in the Device Template table. The Feature Templates column shows the number of feature templates that are included in the device template, and the Type column shows "Feature" to indicate that the device template was created from a collection of feature templates.

## Configuration

Another way to create device templates from feature templates is to first create one or more custom feature templates and then create device templates. You can create multiple feature templates for the same feature. For a list of feature templates, see [Available Feature Templates](#).

1. From the Templates title bar, select Feature.
2. Click the Add Template button.
3. In the left pane, from Select Devices, select the type of device for which you are creating a template. You can create a single feature template for features that are available on multiple device types. You must, however, create separate feature templates for software features that are available only on the device type you are configuring.
4. In the right pane, select the feature template. The template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining required parameters. If the feature has optional parameters, the bottom of the template form shows a plus sign (+) after the required parameters.
5. In the Template Name field, enter a name for the feature template. This field is mandatory and can contain only uppercase and lowercase letters, the digits 0 through 9, hyphens (-), and underscores (\_). It cannot contain spaces or any other characters.
6. In the Description field, enter a description for the feature template. This field is mandatory, and it can contain any characters and spaces.
7. For each required parameter, choose the desired value, and if applicable, select the scope of the parameter. Select the scope from the drop-down menu to the left of each parameter's value box
8. Click the plus sign (+) below the required parameters to set the values of optional parameters.
9. Click Save.
10. Repeat Steps 2 to 9 for each additional feature template you wish to create.
11. From the Templates title bar, select Device.
12. Click the Create Template drop-down and select From Feature Template.
13. From the Device Model drop-down, select the type of device for which you are creating the device template. vManage NMS displays the feature templates for the device type you selected. The required feature templates are indicated with an asterisk (\*). The remaining templates are optional.
14. In the Template Name field, enter a name for the device template. This field is mandatory and can contain only uppercase and lowercase letters, the digits 0 through 9, hyphens (-), and underscores (\_). It cannot contain spaces or any other characters.
15. In the Description field, enter a description for the device template. This field is mandatory, and it can contain any characters and spaces.
16. To view the factory-default configuration for a feature template, select the desired feature template and click View Template. Click Cancel to return to the Configuration Template screen.
17. To use the factory-default configuration, click Create to create the device template. The new device template is displayed in the Device Template table. The Feature Templates column shows the number of feature templates that are included in the device template, and the Type column shows "Feature" to indicate that the device template was created from a collection of feature templates.
18. To modify the factory-default configuration, select the feature template for which you do not wish to use the factory-default template. From the drop-down list of available feature templates, select a feature template that you created.
19. Repeat Step 18 for each factory-default feature template you wish to modify.
20. Click Create. The new configuration template is displayed in the Device Template table. The Feature Templates column shows the number of feature templates that are included in the device template, and the Type column shows "Feature" to indicate that the device template was created from a collection of feature templates.

## Create a Device Template from the CLI

To create a device template by entering a CLI text-style configuration directly on the vManage NMS:

1. In the Device tab, click the Create Template drop-down and select CLI Template.
2. From the Device Type drop-down, select the type of device for which you are creating the template.
3. In the Template Name field, enter a name for the device template. This field is mandatory and can contain only uppercase and lowercase letters, the digits 0 through 9, hyphens (–), and underscores (\_). It cannot contain spaces or any other characters.
4. In the Description field, enter a description for the device template. This field is mandatory, and it can contain any characters and spaces.
5. In the CLI Configuration box, enter the configuration either by typing it, cutting and pasting it, or uploading a file.
6. To convert an actual configuration value to a variable, select the value and click Create Variable. Enter the variable name, and click Create Variable. You can also type the variable name directly, in the format `{{ variable-name }}`; for example, `{{hostname}}`.
7. Click Add. The new device template is displayed in the Device Template table. The Feature Templates column shows the number of feature templates that are included in the device template, and the Type column shows "CLI" to indicate that the device template was created from CLI text.

## Edit a Template

1. In the Device or Feature tab, select a template.
2. Click the More Actions icon to the right of the row and click Edit.

You cannot change the name of a device or feature template when that template is attached to a device.

Note that you can edit templates simultaneously from one or more vManage servers. For simultaneous template edit operations, the following rules apply:

- You cannot edit the same device or feature template simultaneously.
- When you are editing a device template, all other feature templates attached to that device template are locked and you cannot perform any edit operations on them.
- When you are editing a feature template that is attached to a device template, that device template as well as all other feature templates attached to it are locked and you cannot perform any edit operations on them.

## View a Template

1. In the Device or Feature tab, select a template.
2. Click the More Actions icon to the right of the row and click View.

## Delete a Template

1. In the Device or Feature tab, select a template.
2. Click the More Actions icon to the right of the row and click Delete.
3. Click OK to confirm deletion of the template.

## View Device Templates Attached to a Feature Template

1. In the Feature tab, select a template.
2. Click the More Actions icon to the right of the row and click Show Attached Device Templates. The View Attached Device Templates popup window opens, displaying the names of the device templates to which the feature template is attached.

## View Devices Attached to a Device Template

For a device template that you created from feature templates:

1. In the Device tab, select a template.
2. Click the More Actions icon to the right of the row and click Attach Devices.
3. In the Attach Devices window, click the Attached Devices tab.

For a device template that you created from a CLI template:

1. In the Device tab, select a template.
2. Click the More Actions icon to the right of the row and click Show Attached Devices.

## Perform Parallel Template Operations

On Viptela devices in the overlay network, you can perform the same operations, in parallel, from one or more vManage servers. You can perform the following template operations in parallel:

- Attach devices to a device template
- Detach devices from a device template
- Change the variable values for a device template that has devices attached to it

For template operations, the following rules apply:

- When a device template is already attached to a device, you can modify one of its feature templates. Then when you click Update ► Configure Devices, all other template operations—including attach devices, detach devices, and edit device values—are locked on all vManage servers until the update operation completes. This means that a user on another vManage server cannot perform any template operations until the update completes.
- You can perform the attach and detach device template operations on different devices, from one or more vManage servers, at the same time. However, if any one of these operations is in progress on one vManage server, you cannot edit any feature templates on any of the servers until the attach or detach operation completes.

## Attach Devices to a Device Template

To attach one or more devices to a device template:

1. In the Device tab, select a template.
2. Click the More Actions icon to the right of the row and click Attach Devices. The Attach Devices dialog box opens with the Select Devices tab selected
3. In the Available Devices column on the left, select a group and search for one or more devices, select a device from the list, or click Select All.

4. Click the arrow pointing right to move the device to the Selected Devices column on the right.
5. Click Attach.
6. If the template contains variables, enter the missing variable values for each device you selected in one of the following ways:
  - Enter the values manually for each device either in the table column or by clicking the More Actions icon to the right of the row and clicking Edit Device Template. When you are using optional rows, if you do not want to include the parameter for the specific device, do not specify a value.
  - Click Import File in the upper right corner of the screen to upload a CSV file that lists all the variables and defines each variable's value for each device.
7. Click Update
8. Click Next.

If any devices have the same system IP address, a pop-up or an error message is displayed when you click Next. Modify the system IP addresses so that there are no duplicates, and click Save. Then click Next again.
9. In the left pane, select the device, to preview the configuration that is ready to be pushed to the device. The right pane displays the device's configuration and the Config Preview tab in the upper right corner is selected.

Click the Config Diff tab to view the differences between this configuration and the configuration currently running on the device, if applicable.

Click the Back button to edit the variable values entered in the previous screen.
10. If you are attaching a vEdge router, click Configure Device Rollback Timer located at the bottom of the left pane, to configure the time interval at which the device rolls back to its previous configuration if the router loses its control connection to the overlay network. The Configure Device Rollback Time dialog box is displayed.
  - a. From the Devices drop-down, select a device.
  - b. To enable the rollback timer, in the Set Rollback slider beneath the Devices drop-down, drag the slider to the left to enable the rollback timer. When you do this, the slider changes in color from gray to green.
  - c. To disable the rollback timer, click the Enable Rollback slider. When you disable the timer, the Password field pops up. Enter the password that you used to log in to the vManage NMS.
  - d. In the Device Rollback Time slider, drag the slider to the desired value. The default time is 5 minutes. You can configure a time from 6 to 15 minutes.
  - e. To exclude a device from the rollback timer setting, click Add Exception and select the devices to exclude.
  - f. The table at the bottom of the Configure Device Rollback Time dialog box lists all the devices to which you are attaching the template and their rollback time. To delete a configured rollback time, click the Trash icon to right right of the device name.
  - g. Click Save.
11. Click Configure Devices to push the configuration to the devices.

The Status column displays whether the configuration was successfully pushed. Click the right angle bracket to the left of the row to display details of the push operation.

## Copy a Template

1. In the Device or Feature tab, select a template.
2. Click the More Actions icon to the right of the row and click Copy.
3. Enter a new template name and description.
4. Click Copy.

## Edit a CLI Device Template

1. In the Device tab, select a template.
2. Click the More Actions icon to the right of the row and click Edit.
3. In the Device CLI Template window, edit the template.
4. Click Update.

## Export a Variables Spreadsheet in CSV Format for a Template

1. In the Device tab, select a device template.
2. Click the More Actions icon to the right of the row and click Export CSV.

## Change the Device Rollback Timer

By default, when you attach a vEdge router to a configuration template, if the router is unable to successfully start after 5 minutes, it returns to, or rolls back to, the previous configuration. For a configuration that you have created from the CLI, you can change the device's rollback timer:

1. In the Device tab, select a device template.
2. Click the More Actions icon to the right of the row and click Change Device Values. The right pane displays the device's configuration, and the Config Preview tab in the upper right corner is selected.
3. In the left pane, click the name of a device.
4. Click Configure Device Rollback Timer located at the bottom of the left pane. The Configure Device Rollback Time dialog box is displayed.
5. From the Devices drop-down, select a device.
6. To enable the rollback timer, in the Set Rollback slider beneath the Devices drop-down, drag the slider to the left to enable the rollback timer. When you do this, the slider changes in color from gray to green.
7. To disable the rollback timer, click the Enable Rollback slider. When you disable the timer, the Password field pops up. Enter the password that you used to log in to the vManage NMS.
8. In the Device Rollback Time slider, drag the slider to the desired value. The default time is 5 minutes. You can configure a time from 6 to 15 minutes.
9. To exclude a device from the rollback timer setting, click Add Exception and select the devices to exclude.
10. The table at the bottom of the Configure Device Rollback Time dialog box lists all the devices to which you are attaching the template and their rollback time. To delete a configured rollback time, click the Trash icon to right right of the device name.
11. Click Save.
12. Click Configure Devices to push the configuration to the devices. The Status column displays whether the configuration was successfully pushed. Click the right angle bracket to the left of the row to display details of the push operation.

## Preview the Configuration and View Configuration Differences

For a configuration that you have created from the CLI:

---

## Configuration

1. In the Device tab, select a device template.
2. Click the More Actions icon to the right of the row and click Change Device Values. The right pane displays the device's configuration, and the Config Preview tab in the upper right corner is selected.
3. In the left pane, click the name of a device.
4. Click the Config Diff tab to view the differences between this configuration and the configuration currently running on the device, if applicable.  
Click the Back button to edit the variable values entered in the previous screen.
5. Click Configure Devices to push the configuration to the devices.  
The Status column displays whether the configuration was successfully pushed. Click the right angle bracket to the left of the row to display details of the push operation.

## Change Variable Values for a Device

For a configuration that you have created from device configuration templates, if the templates contain variables, the vManage NMS can automatically populate the variables with actual values when you attach the templates to the devices. To do this, you create an Excel file that lists the variable values for each device and save the file in CSV format. You can also enter values for these variables manually.

After you have pushed the configuration to a device, you can change the value assigned to any variable:

1. In the Device tab, select the device template.
2. Click the More Actions icon to the right of the row, and click Change Device Values. The screen displays a table of all the devices that are attached to that device template.
3. For the desired device, click the More Actions icon to the right of the row, and click Edit Device Template.
4. In the Update Device Template pop-up, enter values for the items in the variable list.
5. Click Update.
6. Click Next.
7. Click Configure Devices to push the configuration to the device.  
The Status column displays if the configuration was successfully pushed or not. Click the right angle bracket to the left of the row to display details of the push operation.

## Available Feature Templates

vManage NMS provides the following feature templates to configure Viptela devices in the overlay network:

- [AAA](#)
- [Archive](#)
- [Banner](#)
- [BFD](#)
- [BGP](#)
- [Bridge](#)
- [Cellular Controller](#)
- [Cellular Profile](#)



## Configuration

- [DHCP Server](#)
- [IGMP](#)
- [Logging](#)
- [Multicast](#)
- [NTP](#)
- [OMP](#)
- [OSPF](#)
- [PIM](#)
- [Security](#)
- [SNMP](#)
- [Switch Port](#)
- [System](#)
- [T1/E1 Controller](#)
- [VPN](#)
- [VPN Interface Bridge](#)
- [VPN Interface Cellular](#)
- [VPN Interface DSL PPPoA](#)
- [VPN Interface DSL PPPoE](#)
- [VPN Interface Ethernet](#)
- [VPN Interface GRE](#)
- [VPN Interface IPsec](#)
- [VPN Interface Multilink](#)
- [VPN Interface NAT Pool](#)
- [VPN Interface PPP](#)
- [VPN Interface PPP Ethernet](#)
- [VPN Interface SVI](#)
- [VPN Interface T1/E1](#)
- [WiFi Radio](#)
- [WiFi SSID](#)


## AAA

Use the AAA template for vBond controllers, vManage NMSs, vSmart controllers, vEdge routers, and Cisco IOS XE routers.

Viptela devices support configuration of authentication, authorization, and accounting (AAA) in combination with RADIUS and TACACS+.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Select the Basic Information tab.
6. To create a custom template for AAA, select the Factory\_Default\_AAA\_Template and click Create Template. The AAA template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining AAA parameters.



7. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
8. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
-----------------	-------------------

Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure Authentication Order and Fallback

To configure AAA authentication order and authentication fallback on a Viptela device, select the Authentication tab and configure the following parameters:

1. Parameter Name	Description
Authentication Order	<p>The default order is local, then radius, and then tacacs.</p> <p>To change the default order of authentication methods that the software tries when verifying user access to a Viptela device:</p> <ol style="list-style-type: none"> <li>1. Click the dropdown arrow to display the list of authentication methods.</li> <li>2. In the list, click the up arrows to change the order of the authentication methods and click the boxes to select or deselect a method.</li> </ol> <p>If you select only one authentication method, it must be <b>local</b> .</p>
Authentication Fallback	<p>Click On to configure authentication to fall back from RADIUS or TACACS+ to the next priority authentication method if the user cannot be authenticated or if the RADIUS or TACACS+ servers are unreachable. With the default configuration (Off), authentication falls back only if the RADIUS or TACACS+ servers are unreachable.</p>
Admin Authentication Order	<p>Have the "admin" user use the authentication order configured in the Authentication Order parameter. If you do not configure the admin authentication order, the "admin" user is always authenticated locally.</p>
Disable Netconf Logs	<p>Click On to disable the logging of Netconf events. By default, these events are logged to the auth.info and messages log files.</p>
Disable Audit Logs	<p>Click On to disable the logging of AAA events. By default, these events are logged to the auth.info and messages log files.</p>
RADIUS Server List	<p>List the tags for one or two RADIUS servers. Separate the tags with commas. You set the tag under the RADIUS tab.</p>

*CLI equivalent:*

```
system
aaa
  admin-auth-order
  auth-fallback
  auth-order (local | radius | tacacs)
```

## Configuration

```

logs
  [no] audit-disable
  [no] netconf-disable
radius-servers tag

```

## Configure Local Access for Users and User Groups

To configure local access for individual users, select the Local tab. To add a new user, select the User tab, click Add New User, and configure the following parameters:

Parameter Name	Description
Name	<p>Enter a name for the user. It can be 1 to 128 characters long, and it must start with a letter. The name can contain only lowercase letters, the digits 0 through 9, hyphens (-), underscores (_), and periods (.). The name cannot contain any uppercase letters.</p> <p>The following usernames are reserved, so you cannot configure them: backup, basic, bin, daemon, games, gnats, irc, list, lp, mail, man, news, nobody, proxy, quagga, root, sshd, sync, sys, uucp, and www-data. Also, names that start with viptela-reserved are reserved.</p>
Password	<p>Enter a password for the user. The password is an MD5 digest string, and it can contain any characters, including tabs, carriage returns, and linefeeds. For more information, see <a href="#">Section 9.4</a> in RFC 7950, <i>The YANG 1.1 Data Modeling Language</i>.</p> <p>Each username must have a password. Each user is allowed to change their own password.</p> <p>The default password for the admin user is admin. It is strongly recommended that you change this password.</p>
Description	Enter a description for the user.
User Groups	Select from the list of configured groups. You must assign the user to at least one group. The admin user is automatically placed in the netadmin group and is the only member of this group.

Click Add to add the new user. Click Add New User again to add additional users.

To configure local access for user groups, you first place the user into either the basic or operator group. The admin is automatically placed in the netadmin group. Then you configure user groups. To do this, select the Local tab, select the User Group tab, click Add New User Group, and configure the following parameters:

Parameter Name	Description
Name	<p>Name of an authentication group. It can be 1 to 128 characters long, and it must start with a letter. The name can contain only lowercase letters, the digits 0 through 9, hyphens (-), underscores (_), and periods (.). The name cannot contain any uppercase letters.</p> <p>The Viptela software provides three standard user groups, basic, netadmin, and operator. The user admin is automatically placed in the group netadmin and is the only user in this group. All users learned from a RADIUS or TACACS+ server are placed in the group basic. All users in the basic group have the same permissions to perform tasks, as do all users in the operator group.</p> <p>The following groups names are reserved, so you cannot configure them: adm, audio, backup, bin, cdrom, dialout, dip, disk, fax, floppy, games, gnats, input, irc, kmem, list, lp, mail, man, news, nogroup, plugdev, proxy, quagga, quaggavty, root, sasl, shadow, src, sshd, staff, sudo, sync, sys, tape, tty, uucp, users, utmp, video, voice, and www-data. Also, group names that start with the string viptela-reserved are reserved.</p>
Feature	The feature table lists the roles for the user group. These roles are Interface, Policy, Routing, Security, and System. Each role allows the user group to read or write specific portions of the device's configuration and to execute specific types of operational commands. Click the appropriate boxes for Read, Write, and None to assign privileges to the group for each role.

Click Add to add the new user group.

To add another user group, click Add New User Group again.

## Configuration

To delete a user group, click the trash icon at the right side of the entry. You cannot delete the three standard user groups, basic, netadmin, and operator.

*CLI equivalent:*

```
system
aaa
  user username
  group group-name
  password password
  usergroup group-name
  task (interface | policy | routing | security | system) (read | write)
```

## Configure RADIUS Authentication

To configure RADIUS authentication, select the RADIUS tab and configure the following parameters:

Parameter Name	Description
Retransmit Count	Specify how many times to search through the list of RADIUS servers while attempting to locate a server.  <i>Range: 1 through 1000</i> <i>Default: 3</i>
Timeout	Specify how long to wait to receive a reply from the RADIUS server before retransmitting a request.  <i>Range: 1 through 1000</i> <i>Default: 5 seconds</i>

To configure a connection to a RADIUS server, select the RADIUS tab, click Add New Radius Server, and configure the following parameters:

Parameter Name	Description
Address	Enter the IP address of the RADIUS server host.
Tag	Enter a text string to identify the RADIUS server. The tag can be 4 to 16 characters long. The tag allows you to configure authentication for AAA, IEEE 802.1X, and IEEE 802.11i to use a specific RADIUS server or servers. For Cisco routers running Viptela software, this field is ignored.
Authentication Port	Enter the UDP destination port to use for authentication requests to the RADIUS server. If the server is not used for authentication, configure the port number to be 0. <i>Default: Port 1812</i>
Accounting Port	Enter the UDP port to use to send 802.1X and 802.11i accounting information to the RADIUS server. <i>Range: 0 through 65535</i> <i>Default: 1813</i>
Key (Deprecated)	This field is deprecated. Use the Secret Key field instead.
Secret Key	Enter the key the Viptela device passes to the RADIUS server for authentication and encryption. You can type the key as a text string from 1 to 32 characters long, and it is immediately encrypted, or you can type an AES 128-bit encrypted key. The key must match the AES encryption key used on the RADIUS server.
Source Interface	Enter the name of the interface on the local device to use to reach the RADIUS server.
VPN ID	Enter the number of the VPN in which the RADIUS server is located or through which the server can be reached. If you configure multiple RADIUS servers, they must all be in the same VPN.

Priority	Enter the priority of a RADIUS server. A server with a lower number is given priority. <i>Range:</i> 0 through 7 <i>Default:</i> 0
----------	--

Click Add to add the new RADIUS server.

To add another RADIUS server, click Add New RADIUS Server again.

To remove a server, click the trash icon on the right side of the line.

*CLI equivalent:*

```

system
 radius
  retransmit number
  server ip-address
  acct-port port-number
  auth-port port-number
  priority number
  secret-key key
  source-interface interface-name
  tag tag
  vpn vpn-id
  timeout seconds

```

## Configure TACACS+ Authentication

To configure the device to use TACACS+ authentication, select the TACACS tab and configure the following parameters:

Parameter Name	Description
Timeout	Enter how long to wait to receive a reply from the TACACS+ server before retransmitting a request. <i>Range:</i> 1 through 1000 <i>Default:</i> 5 seconds
Authentication	Set the type of authentication to use for the server password. The default authentication type is PAP. You can change it to ASCII.

To configure a connection to a TACACS+ server, select the TACACS tab, click Add New TACSCS Server, and configure the following parameters:

Parameter Name	Description
Address	Enter the IP address of the TACACS+ server host.
Authentication Port	Enter the UDP destination port to use for authentication requests to the TACACS+ server. If the server is not used for authentication, configure the port number to be 0. <i>Default:</i> Port 49
Key (Deprecated)	This field is deprecated. Use the Secret Key field instead.
Secret Key	Enter the key the Viptela device passes to the TACACS+ server for authentication and encryption. You can type the key as a text string from 1 to 32 characters long, and it is immediately encrypted, or you can type an AES 128-bit encrypted key. The key must match the AES encryption key used on the TACACS+ server.
Source Interface	Enter the name of the interface on the local device to use to reach the TACACS+ server.

## Configuration

VPN ID	VPN in which the TACACS+ server is located or through which the server can be reached. If you configure multiple TACACS+ servers, they must all be in the same VPN.
Priority	Set the priority of a TACACS+ server. A server with lower priority number is given priority over one with a higher number. <i>Range: 0 through 7</i> <i>Default: 0</i>

Click Add to add the new TACACS server.

To add another TACACS server, click Add New TACACS Server again.

To remove a server, click the trash icon on the right side of the line.

*CLI equivalent:*

```
system
 tacacs
  authentication password-authentication
  server ip-address
  auth-port port-number
  priority number
  key key
  source-interface interface-name
  vpn vpn-id
  timeout seconds
```

## Release Information

Introduced in vManage NMS in Release 15.2.

In Release 17.1, add Disable Netconf Logs and Disable Audit Logs fields.


## Archive

Use the Archive template for vBond controllers, vManage NMSs, vSmart controllers, and vEdge routers.

You can configure a Viptela device to periodically archive a copy of the full running configuration to an archival file. The running configuration that is archived is viewable by the user "admin".

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Under Additional System Templates, located to the right of the screen, click Archive.
6. From the Archive drop-down, click Create Template. The Archive template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining Archive parameters.



7. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
8. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>



## Configure Configuration Archive Configuration

To configure archiving of running configurations, configure the following parameters:

Parameter Name	Description
Archival Interval	Specify how often to archive the full running configuration. In addition, the running configuration is archived each time you issue the <b>commit</b> command on the device. <i>Range:</i> 5 minutes through 525600 minutes (about one year) <i>Default:</i> 10080 minutes (7 days)
Path to Archive File Directory	Specify the path to the directory in which to store the archival file and the base name of the file. The path can be one of the following: <ul style="list-style-type: none"> <li>• <b>ftp:</b> <i>file-path</i> —Path to a file on an FTP server.</li> <li>• <b>scp:</b> <i>user @ host : file-path</i></li> <li>• <b>path</b> <i>file-path / filename / file-path / filename</i> —Path to a file on the local Viptela device.</li> </ul> A separate file is created for each archiving operation. To distinguish the files, a timestamp is appended to the filename. The timestamp has the format <i>yyyy - mm - dd _ hh - mm - ss</i> .
SSH Key File	Enter the name of the SSH private key file on the local Viptela device. This file is used to SCP into a remote file server. The Viptela software automatically generates a public and a private key and places the public key in the SSH key file <i>archive_id_rsa.pub</i> , which is located in <i>/home/admin</i> directory on the Viptela device. If you do not enter the name of an SSH private key file, the software uses the automatically generated private key.
VPN ID	Enter the ID for the VPN in which the archival file server is located or through which the server can be reached. On vEdge routers, <i>vpn-id</i> can be a value from 0 through 65530. On vSmart controllers, <i>vpn-id</i> can be either 0 or 512.

To save the feature template, click Save.

*CLI equivalent:*

```
system
archive
  interval minutes
  path file-path
  ssh-id-file filename
  vpn vpn-id
```

## Release Information

Introduced in vManage NMS in Release 15.2.

## Banner

Use the Banner template for vBond controllers, vManage NMSs, vSmart controllers, vEdge routers, and Cisco IOS XE routers.

You can configure two different banner text strings, one to be displayed before the CLI login prompt on a Viptela device and the other to be displayed after a successful login to the device.


- To configure the banner text for login screens using vManage templates, create a Banner feature template to configure PIM parameters, as described in this article.
- To configure a login banner for the vManage NMS system, see the Administration ► [Settings](#) help file.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.

Configuration

3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Additional Templates tab located directly beneath the Description field, or scroll to the Additional Templates section.
6. From the Banner drop-down, click Create Template. The Banner template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining Banner parameters.



7. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
8. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
-----------------	-------------------

Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure the Banner

To set a banner, configure the following parameters:

Parameter Name	Description
Login Banner	Enter text to display before the login prompt. The string can be up to 2048 characters long. To insert a line break, type <code>\n</code> .
MOTD Banner	Enter message-of-the-day text to display after a successful login. The string can be up to 2048 characters long. To insert a line break, type <code>\n</code> .

To save the feature template, click Save.

*CLI equivalent:*

```
banner
  login "text"
  motd "text"
```

## Release Information

Introduced in vManage NMS in Release 15.2.

## BFD

Use the BFD template for vEdge routers and Cisco IOS XE routers.


The BFD protocol, which detects link failures as part of the Viptela high availability solution, is enabled by default on all vEdge routers, and you cannot disable it.

## Navigate to the Template Screen

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.

Configuration

4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. To create a custom template for BFD, select the Factory\_Default\_BFD\_Template and click Create Template. The BFD template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining BFD parameters. You may need to click a tab or the plus sign (+) to display additional fields.
6. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.



7. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>

## Configuration

Global (indicated by a globe icon)	Enter a value for the parameter, and apply that value to all devices.  Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.
------------------------------------	--

## Configure BFD for Application-Aware Routing

To configure the BFD timers used by application-aware routing, click the Basic Configuration tab and configure the following parameters:

Parameter Name	Description
Multiplier	Specify the value by which to multiply the poll interval, to set how often application-aware routing acts on the data plane tunnel statistics to figure out the loss and latency and to calculate new tunnels if the loss and latency times do not meet configured SLAs. <i>Range:</i> 1 through 6 <i>Default:</i> 6
Poll Interval	Specify how often BFD polls all data plane tunnels on a vEdge router to collect packet latency, loss, and other statistics used by application-aware routing. <i>Range:</i> 1 through 4,294,967,296 ( $2^{32} - 1$ ) milliseconds <i>Default:</i> 600,000 milliseconds (10 minutes)

To save the feature template, click Save.

*CLI equivalent:*

```
bfd app-route
  multiplier number
  poll-interval milliseconds
```

## Configure BFD on Transport Tunnels

To configure the BFD timers used on transport tunnels, click the Color tab, click Add New Color, and configure the following parameters:

Parameter Name	Description
Color	From the drop-down, choose the color of the transport tunnel for data traffic moving between vEdge routers. The color identifies a specific WAN transport provider. <i>Values:</i> 3g, biz-internet, blue, bronze, custom1, custom2, custom3, default, gold, green, lte, metro-ethernet, mpls, private1 through private6, public-internet, red, silver <i>Default:</i> default
Hello Interval	Specify how often BFD sends Hello packets on the transport tunnel. BFD uses these packets to detect the liveness of the tunnel connection and to detect faults on the tunnel. <i>Range:</i> 100 through 60000 milliseconds <i>Default:</i> 1000 milliseconds (1 second)
Multiplier	Specify how many Hello packet intervals BFD waits before declaring that a tunnel has failed. BFD declares that the tunnel has failed when, during all these intervals, BFD has received no Hello packets on the tunnel. This interval is a multiplier of the Hello packet interval time. <i>Range:</i> 1 through 60 <i>Default:</i> 7 (for hardware vEdge routers), 20 (for vEdge Cloud software routers)
Path MTU Discovery	Click On to enable path MTU discovery for the transport tunnel, or Off to disable. When PMTU discovery is enabled, the path MTU for the tunnel connection is checked periodically, about once per minute, and it is updated dynamically. When PMTU discovery is disabled, the expected tunnel MTU is 1472 bytes, but the effective tunnel MTU is 1468 bytes. <i>Default:</i> Enabled

Add	Click Add to save the data traffic transport tunnel color.
-----	--

To add another color, click Add New Color.

A table lists the transport tunnel colors.

To edit a color, click the Pencil icon. The Update Color popup is displayed. After you make the desired changes, click Save Changes.

To remove a color, click the trash icon to the right of the entry.

To save the feature template, click Save.

*CLI equivalent:*

```
bfd color color
  hello-interval milliseconds
  multiplier number
  pmtu-discovery
```

## Release Information

Introduced in vManage NMS in Release 15.2.

## BGP

Use the BGP template for all vEdge Cloud and vEdge router devices.

To configure the BGP routing protocol using vManage templates:


1. Create a BGP feature template to configure BGP parameters, as described in this article. BGP can be used for service-side routing, to provide reachability to networks at the local site, and it can be used for transport-side routing, to enable communication between the vEdge router and other Viptela devices when the router is not directly connected to the WAN cloud. Create separate BGP templates for the two BGP routing types.
2. Create a VPN feature template to configure VPN parameters for either service-side BGP routing (in any VPN other than VPN 0 or VPN 512) or transport-side BGP routing (in VPN 0). See the [VPN](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. To create a template for VPN 0 or VPN 512:
  - a. Click the Transport & Management VPN tab located directly beneath the Description field, or scroll to the Transport & Management VPN section.
  - b. Under Additional VPN 0 Templates, located to the right of the screen, click BGP.
  - c. From the BGP drop-down, click Create Template. The BGP template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining BGP parameters.
6. To create a template for VPNs 1 through 511, and 513 through 65530:

Configuration

- a. Click the Service VPN tab located directly beneath the Description field, or scroll to the Service VPN section.
- b. Click the Service VPN drop-down.
- c. Under Additional VPN Templates, located to the right of the screen, click BGP.
- d. From the BGP drop-down, click Create Template. The BGP template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining BGP parameters.



7. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
8. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
-----------------	-------------------

Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure Basic BGP

The following parameters are required (unless otherwise indicated) to configure BGP on a vEdge router:

To configure BGP, select the Basic Configuration tab and configure the following parameters. Parameters marked with an asterisk are required to configure BGP.

Parameter Name	Description
Shutdown*	Ensure that No is selected, to enable BGP.
AS number*	Enter the local AS number.
Router ID	Enter the BGP router ID, in decimal four-part dotted notation.
Propagate AS Path	Click On to carry BGP AS path information into OMP.
Internal Routes Distance	Enter a value to apply as the BGP route administrative distance for routes coming from one AS into another. <i>Range: 0 through 255</i> <i>Default: 0</i>
Local Routes Distance	Specify the BGP route administrative distance for routes within the local AS. By default, a route received locally from BGP is preferred over a route received from OMP. <i>Range: 0 through 255</i> <i>Default: 0</i>
External Routes Distance	Specify the BGP route administrative distance for routes learned from other sites in the overlay network. <i>Range: 0 through 255</i> <i>Default: 0</i>

For service-side BGP, you might want to configure OMP to advertise to the vSmart controller any BGP routes that the vEdge router learns. By default, a vEdge router advertises to OMP both the connected routes on the vEdge router and the static routes that are configured on the vEdge router, but it does not advertise BGP external routes learned by the vEdge router. You configure this route advertisement in the OMP template for vEdge routers or vEdge software. See the OMP help topic.

For transport-side BGP, you must also configure a physical interface and a loopback interface in VPN 0. In addition, you should create a policy for BGP to advertise the loopback interface address to its neighbors, and apply the policy in the BGP instance or to a specific neighbor. See the [Configuring Unicast Overlay Routing](#) article for your software release.

To save the feature template, click Save.

*CLI equivalent:*



## Configuration

```

vpn vpn-id
router
  bgp local-as-number
    distance
      external number
      internal number
      local number
  propagate-aspath
  router-id ip-address
  [no] shutdown

```

## Configure the IPv4 Unicast Address Family

To configure global BGP address family information, select the IPv4 Unicast Address Family tab and configure the following parameters:

### Tab

#### Parameter Name

#### Description

#### Maximum Paths

Specify the maximum number of parallel IBGP paths that can be installed into a route table to enable IBGP multipath load sharing.

*Range:* 0 to 32

#### Address Family

Enter the BGP IPv4 unicast address family. Currently, only IPv4 is supported.

### Redistribute

Click the Redistribute tab, and then click Add New Redistribute.

#### Protocol

Select the protocols from which to redistribute routes into BGP, for all BGP sessions. Options are Connected, NAT, OMP, OSPF, and Static. At a minimum, select the following:

- For service-side BGP routing, select OMP. By default, OMP routes are not redistributed into BGP.
- For transport-side BGP routing, select Connected, and then under Route Policy, specify a route policy that has BGP advertise the loopback interface address to its neighbors.

#### Route Policy

Enter the name of the route policy to apply to redistributed routes.

Click Add to save the redistribution information.

### Network

Click the Network tab, and then click Add New Network.

#### Network Prefix

Enter a network prefix, in the format of *prefix/length*, to be advertised by BGP.

Click Add to save the network prefix.

### Aggregate Address

## Configuration

Click the Aggregate Address tab, and then click Add New Aggregate Address.

#### Aggregate Prefix

Enter the prefix of the addresses to aggregate for all BGP sessions, in the format *prefix/length*.

#### AS Set Path

Click On to generate set path information for the aggregated prefixes.

#### Summary Only

Click On to filter out more specific routes from BGP updates.

Click Add to save the aggregate address.

To save the feature template, click Save.

#### CLI equivalent:

```
vpn vpn-id
router
  bgp local-as-number
  address-family ipv4-unicast
  aggregate-address prefix/length [as-set] [summary-only]
  maximum-paths paths number
  network prefix/length
  redistribute (connected | nat | omp | ospf | static)
```

## Configure Neighbors

To configure a neighbor, select the Neighbor tab and click Add New Neighbor and configure the following parameters. For BGP to function, you must configure at least one neighbor.

Parameter Name	Description
Address	Specify the IP address of the BGP neighbor.
Description	Enter a description of the BGP neighbor.
Remote AS	Enter the AS number of the remote BGP peer.

Address Family	<p>Click On and select the address family. Currently, the Viptela software supports only the BGP IPv4 unicast address family. Enter the address family information:</p> <ul style="list-style-type: none"> <li>Address Family—Select the address family. Currently, the Viptela software supports only the BGP IPv4 unicast address family.</li> <li>Maximum Number of Prefixes—Specify the maximum number of prefixes that can be received from the neighbor. <i>Range:</i> 1 through 4294967295 <i>Default:</i> 0 If you specify a maximum number of prefixes, you can also configure: <ul style="list-style-type: none"> <li>Threshold—Threshold at which to generate a warning message or restart the BGP connection. The threshold is a percentage of the maximum number of prefixes.</li> <li>Restart Interval—How long to wait to restart the BGP connection. <i>Range:</i> 1 through 65535 minutes</li> <li>Warning Only—Click On to only display a warning message, without restarting the BGP connection. You can specify either a restart interval or a warning only.</li> </ul> </li> <li>Route Policy In—Click On and specify the name of a route policy to apply to prefixes received from the neighbor.</li> <li>Route Policy Out—Click On and specify the name of a route policy to apply to prefixes sent to the neighbor.</li> </ul>
Shutdown	Click On to enable the connection to the BGP neighbor.

To configure advanced parameters for the neighbor, click the Neighbor tab, and then click Advanced Options:

Parameter Name	Description
Next-Hop Self	Click On to configure the router to be the next hop for routes advertised to the BGP neighbor.
Send Community	Click On to send the local router's BGP community attribute to the BGP neighbor.
Send Extended Community	Click On to send the local router's BGP extended community attribute to the BGP neighbor.
Negotiate Capability	Click On to allow the BGP session to learn about the BGP extensions that are supported by the neighbor.
Source Interface Address	Enter the IP address of a specific interface of the neighbor that BGP is to use for the TCP connection to the neighbor.
Source Interface Name	Enter the name of a specific interface of the neighbor that BGP is to use for the TCP connection to the neighbor, in the format <b>ge port / slot</b> .
EBGP Multihop	Set the time to live (TTL) for BGP connections to external peers. <i>Range:</i> 0 to 255 <i>Default:</i> 1
Password	Enter a password to use to generate an MD5 message digest. Configuring the password enables MD5 authentication on the TCP connection with the BGP peer. The password is case-sensitive and can be up to 25 characters long. It can contain any alphanumeric characters, including spaces. The first character cannot be a number.
Keepalive Time	Specify the frequency at which keepalive messages are advertised to a BGP peer. These messages indicate to the peer that the local router is still active and should be considered to be available. Specify the keepalive time for the neighbor, to override the global keepalive time. <i>Range:</i> 0 through 65535 seconds <i>Default:</i> 60 seconds (one-third the hold-time value)

Hold Time	Specify the interval after not receiving a keepalive message that the local BGP session considers its peer to be unavailable. The local router then terminates the BGP session to that peer. Specify the hold time for the neighbor, to override the global hold time. <i>Range:</i> 0 through 65535 seconds <i>Default:</i> 180 seconds (three times the keepalive timer)
Connection Retry Time	Specify the number of seconds between retries to establish a connection to a configured BGP neighbor peer that has gone down. <i>Range:</i> 0 through 65535 seconds <i>Default:</i> 30 seconds
Advertisement Interval	For the BGP neighbor, set the minimum route advertisement interval (MRAI) between when BGP routing update packets are sent to that neighbor. <i>Range:</i> 0 through 600 seconds <i>Default:</i> 5 seconds for IBGP route advertisements; 30 seconds for EBGP route advertisements

To save the feature template, click Save.

**CLI equivalent:**

```
vpn vpn-id
router
  bgp local-as-number
  neighbor ip-address
    address-family ipv4-unicast
      maximum-prefixes number [threshold] [restart minutes | warning-only]
      route-policy policy-name (in | out)
    capability-negotiate
    description string
    ebgp-multihop ttl
    next-hop-self
    password md5-digest-string
    remote-as remote-as-number
    send-community
    send-ext-community
    [no] shutdown
    timers
      advertisement-interval number
      connect-retry seconds
      holdtime seconds
      keepalive seconds
    update-source ip-address
```

## Configure Advanced Parameters

To configure advanced parameters for BGP, click the Advanced tab and configure the following parameters:

Parameter Name	Description
Hold Time	Specify the interval after not receiving a keepalive message that the local BGP session considers its peer to be unavailable. The local router then terminates the BGP session to that peer. This hold time is the global hold time. <i>Range:</i> 0 through 65535 seconds <i>Default:</i> 180 seconds (three times the keepalive timer)
Keepalive	Specify the frequency at which keepalive messages are advertised to a BGP peer. These messages indicate to the peer that the local router is still active and should be considered to be available. This keepalive time is the global keepalive time. <i>Range:</i> 0 through 65535 seconds <i>Default:</i> 60 seconds (one-third the hold-time value)

Compare MED	Click On to compare the router IDs among BGP paths to determine the active path.
Deterministic MED	Click On to compare MEDs from all routes received from the same AS regardless of when the route was received.
Missing MED as Worst	Click On to consider a path as the worst path if the path is missing a MED attribute.
Compare Router ID	Click On to always compare MEDs regardless of whether the peer ASs of the compared routes are the same.
Multipath Relax	Click On to have the BGP best-path process select from routes in different in ASs. By default, when you are using BGP multipath, the BGP best path process selects from routes in the same AS to load-balance across multiple paths.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
router
  bgp local-as-number
  best-path
    as-path multipath-relax
    compare-router-id
  med (always-compare | deterministic | missing-as-worst)
timers
  holdtime seconds
  keepalive seconds
```

## Release Information

Introduced in vManage NMS in Release 15.2.

In Release 17.1, add Propagate AS Path field.

## Bridge

Use the Bridge template for all vEdge Cloud and vEdge router devices.

To have a vEdge router act as a transparent bridge, configure bridging domains on the router. A router can have up to 16 bridging domains.


To configure the bridging domains using vManage templates:

1. Create a Bridge feature template, as described in this article.
2. Create a VPN Interface Bridge feature template to enable integrated routing and bridging (IRB). See the [VPN Interface Bridge](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Additional Templates tab located directly beneath the Description field, or scroll to the Additional Templates section.

- Click the plus sign (+) next to Bridge.



- From the Bridge drop-down, click Create Template. The Bridge template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining Bridge parameters.
- In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
- In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>

## Configuration

Global (indicated by a globe icon)	Enter a value for the parameter, and apply that value to all devices.  Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.
------------------------------------	--

## Configure Bridging Domains

To configure bridging domains, select the Basic Configuration tab and configure the following parameters. For bridging to work, you must also associate interfaces with the bridging domain. Parameters marked with an asterisk are required to configure bridging.

Parameter Name	Description
Bridge Name*	Enter a text description of the bridging domain. It can be up to 32 characters.
VLAN ID*	Enter the VLAN identifier to associate with the bridging domain. <i>Range:</i> 0 through 4095
Maximum MAC Addresses	Specify the maximum number of MAC addresses that the bridging domain can learn. <i>Range:</i> 0 through 4096 <i>Default:</i> 1024
Age-Out Time	Specify how long to store an entry in the MAC table before it ages out. <i>Range:</i> 10 through 4096 seconds <i>Default:</i> 300 seconds (5 minutes)

To save the feature template, click Save.

### CLI equivalent:

```
bridge bridge-id
  age-time seconds
  max-macs number
  name text
  vlan number
```

## Associate Interfaces with the Bridge Domain

To associate an interface with the bridge domain, click the Interface tab and click Add New Interface:

Parameter Name	Description
Interface Name*	Enter the name of the interface to associate with the bridging domain, in the format <b>ge slot / port</b> .
Description	Enter a text description of the interface.
Native VLAN Support	Click Enabled to configure the interface to carry untagged traffic. By default, native VLAN is disabled.
Shutdown	Click No to enable the interface. By default, an interface in a bridge domain is disabled.
Static MAC Address	Click Add Static MAC Address, and in the MAC Static Address field that appears, enter a static MAC address entry for the interface in the bridge domain. Click Add MAC Address to add another static MAC address entry for the interface. Click Save to save the MAC address or addresses.

To save the feature template, click Save.

### CLI equivalent:

---

## Configuration

```
bridge bridge-id
interface interface-name
  description "text description"
  native-vlan
  [no] shutdown
  static-mac-address mac-address
```

## Release Information

Introduced in vManage NMS in Release 15.3.

## Cellular Controller


Use the Cellular Controller template for Cisco IOS XE routers running the SD-WAN software.

To use vManage templates to configure a cellular controller for a 4G network interface module (NIM) installed in a router, create a Cellular Controller template to configure cellular controller properties. This template is mandatory if the 4G NIM module is installed in the router.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Select the Cellular tab.
6. To create a cellular controller template, in the Cellular Controller drop-down click Create Template. The Cellular Controller template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining cellular controller parameters.





7. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
8. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure a Cellular Controller

To configure a cellular controller, configure the following parameters. Parameters marked with an asterisk are required to configure an interface.

Parameter Name	Description
Cellular ID*	Enter the interface slot and port number in which the cellular NIM card is installed. Currently, it can be 0/1/0 or 0/2/0.
Primary SIM Slot*	Enter the number of the primary SIM slot. It can be 0 or 1. The other slot is automatically set to be the secondary. If there is a single SIM slot, this parameter is not applicable.
SIM Failover Retries	Specify the maximum number of times to retry connecting to the secondary SIM when service on the primary SIM becomes unavailable. If there is a single SIM slot, this parameter is not applicable.  <i>Range:</i> 0 through 65535 <i>Default:</i> 10
SIM Failover Timeout	Specify how long to wait before switching from the primary SIM to the secondary SIM if service on the primary SIM becomes unavailable. If there is a single SIM slot, this parameter is not applicable.  <i>Range:</i> 3 to 7 minutes <i>Default:</i> 3 minutes

To save the feature template, click Save.

## Release Information

Introduced in vManage NMS Release 18.1.1.

## Cellular Profile

Use the Cellular Profile feature template to configure the profiles used by cellular modems on vEdge routers and Cisco IOS XE routers running the SD-WAN software.

To configure a cellular profile using vManage templates:


1. Create a Cellular Profile template to configure the profiles used by the cellular modem, as described in this article.
2. Create a VPN-Interface-Cellular feature template to configure cellular module parameters. See the [VPN-Interface-Cellular](#) help topic.
3. Create a VPN feature template to configure VPN parameters. See the [VPN](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Additional Templates tab located directly beneath the Description field, or scroll to the Additional Templates section.

Configuration

- Click the plus sign (+) next to Cellular-Profile.



- From the Cellular-Profile drop-down, click Create Template. The Cellular-Profile template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining Cellular-Profile parameters.
- In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
- In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>

Global (indicated by a globe icon)	Enter a value for the parameter, and apply that value to all devices.  Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.
------------------------------------	--

## Configure a Cellular Profile

To configure a cellular profile, in the Basic Configuration tab, configure the following parameters. Parameters marked with an asterisk are required to configure the cellular profile.

Parameter Name	Description
Interface name*	Enter the name of the cellular interface, which must be cellular0.
Profile ID*	Enter the identification number of the profile to use on the router. You use this profile identification number when you configure for the cellular interface in the VPN-Interface-Cellular template. <i>Range:</i> 1 through 15
Access Point Name	Enter the name of the gateway between the service provider network and the public Internet. It can be up to 32 characters long.
Authentication	Select the authentication method used for the connection to the cellular network. It can be CHAP, None, PAP, or PAP/CHAP.
IP Address (on vEdge routers)	Enter the static IP address assigned to the cellular interface. This field is used when the service provider requires that a static IP address be preconfigured before attaching to the network.
Profile Name (on vEdge routers)	Enter a name to identify the cellular profile. It can be up to 14 characters long.
Packet Data Network Type	Select the packet data network (PDN) type of the cellular network. It can be IPv4, IPv6, or IPv46.
Profile Username	Enter the username to use when making cellular connections for web services. It can be 1 to 32 characters. It can contain any alphanumeric characters, including spaces.
Profile Password	Enter the user password to use when making cellular connections for web services. The password is case-sensitive and can be clear text, or an AES encrypted key.
Primary DNS Address (on vEdge routers)	Enter the IP addresses of the primary DNS servers in the service provider network, in decimal four-part dotted notation.
Overwrite (on IOS XE routers)	Click On to overwrite the profile on the cellular modem.

To save the feature template, click Save.

### CLI equivalent:

```
cellular cellular0
  profile number
    apn name
    auth auth-method
    ip-addr ip-address
    name profile-name
    pdn-type type
    primary-dns ip-address
    secondary-dns ip-address
    user-name user-name
    user-pass password
```

## Release Information

Introduced in vManage NMS in Release 16.1.

## DHCP Server

Use the DHCP-Server template for all vEdge Cloud and vEdge router devices.

You enable DHCP server functionality on a vEdge router interface so it can assign IP addresses to hosts in the service-side network.


To configure a vEdge router to act as a DHCP server using vManage templates:

1. Create a DHCP-Server feature template to configure DHCP server parameters, as described in this article.
2. Create one or more interface feature templates, as described in the [VPN-Interface-Ethernet](#) and the [VPN-Interface-PPP-Ethernet](#) help topics.
3. Create a VPN feature template to configure VPN parameters. See the [VPN](#) help topic.

To configure a vEdge router interface to be a DHCP helper so that it forwards broadcast DHCP requests that it receives from DHCP servers, in the DHCP Helper field of the applicable interfaces template, enter the addresses of the DHCP servers.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Service VPN tab located directly beneath the Description field, or scroll to the Service VPN section.
6. Click the Service VPN drop-down.
7. Under Additional VPN Templates, located to the right of the screen, click VPN Interface.
8. From the Sub-Templates drop-down, select DHCP Server.
9. From the DHCP Server drop-down, click Create Template. The DHCP-Server template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining DHCP Server parameters.



10. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
11. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Minimum DHCP Server Configuration

To configure DHCP server functionality, select the Basic Configuration tab and configure the following parameters. Parameters marked with an asterisk as required to configure DHCP servers.

Parameter Name	Description
Address Pool*	Enter the IPv4 prefix range, in the format <i>prefix/length</i> , for the pool of addresses in the service-side network for which the vEdge router interface acts as DHCP server.
Exclude Addresses	Enter one or more IP addresses to exclude from the DHCP address pool. To specify multiple individual addresses, list them separated by a comma (for example, 1.1.1.1, 2.2.2.2, 3.3.3.3). To specify a range of addresses, separate them with a hyphen (for example, 1.1.1.1-1.1.1.10).
Maximum Leases	Specify the number of IP addresses that can be assigned on this interface. <i>Range:</i> 0 through 4294967295
Lease Time	Specify how long a DHCP-assigned IP address is valid. <i>Range:</i> 0 through 4294967295 seconds
Offer Time	Specify how long the IP address offered to a DHCP client is reserved for that client. By default, an offered IP address is reserved indefinitely, until the DHCP server runs out of addresses. At that point, the address is offered to another client. <i>Range:</i> 0 through 4294967295 seconds <i>Default:</i> 600 seconds
Administrative State	Select Up to enable or Down to disable the DHCP functionality on the interface. By default, DHCP server functionality is disabled on a vEdge router interface.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  interface geslot/port
    dhcp-server
      address-pool prefix/length
      admin-state (down | up)
      exclude ip-address
      lease-time seconds
      max-leases number
      offer-time minutes
```

## Configure Static Leases

To configure a static lease to assign a static IP address to a client device on the service-side network, click the Static Lease tab. Then click Add New Static Lease and configure the following parameters:

Parameter Name	Description
MAC Address	Enter the MAC address of the client to which the static IP address is being assigned.
IP Address	Enter the static IP address to assign to the client.
Hostname	Enter the hostname of the client device.

To edit a static lease, click the pencil icon to the right of the entry.

To remove a static lease, click the trash icon to the right of the entry.

To save the feature template, click Save.

*CLI equivalent:*

## Configuration

```
vpn vpn-id
  interface geslot/port
    dhcp-server
      static-lease mac-address ip ip-address host-name hostname
```

## Configure Advanced Options

To configure a advanced DHCP server options, click the Advanced tab and then configure the following parameters:

Parameter Name	Description
Interface MTU	Specify the maximum MTU size of packets on the interface. <i>Range: 68 to 65535 bytes</i>
Domain Name	Specify the domain name that the DHCP client uses to resolve hostnames.
Default Gateway	Enter the IP address of a default gateway in the service-side network.
DNS Servers	Enter one or more IP address for a DNS server in the service-side network. Separate multiple entries with a comma. You can specify up to eight addresses.
TFTP Servers	Enter the IP address of a TFTP server in the service-side network. You can specify one or two addresses. If two, separate them with a comma.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  interface geslot/port
    dhcp-server
      options
        default-gateway ip-address
        dns-servers ip-address
        domain-name domain-name
        interface-mtu mtu
        tftp-servers ip-address
```

## Release Information

Introduced in vManage NMS in Release 15.2.

## GPS

Use the GPS template for all Cisco cellular routers running Viptela software.

For Cisco devices running Viptela software, you can configure the GPS and National Marine Electronics Association (NMEA) streaming. You enable both these features to allow 4G LTE routers to obtain GPS coordinates.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.



## Configuration

4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Select the Cellular tab.
6. In Additional Cellular Controller Templates, click GPS.
7. To create a custom template for GPS, click the GPS drop-down and then click Create Template. The GPS template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining GPS parameters.
8. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
9. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure GPS

To configure GPS parameters for the cellular router, configure the following parameters. Parameters marked with an asterisk are required to configure the GPS feature.

Parameter Name	Description
GPS	Click On to enable the GPS feature on the router.
GPS Mode	<p>Select the GPS mode:</p> <ul style="list-style-type: none"> <li>• MS-based—Use mobile station–based assistance, also called assisted GPS mode, when determining position. In this mode, cell tower data is used to enhance the quality and precision in determining location, which is useful when satellite signals are poor.</li> <li>• Standalone—Use satellite information when determining position.</li> </ul>
NMEA	Click On to enable the use of NMEA streams to help in determining position. NMEA streams data from the router's 4G LTE NIM to any marine device, such as a Windows-based PC, that is running a commercially available GPS-based application.

Source Address	Enter the IP address of the interface that connects to the router's NIM.
Destination Address	Enter the IP address of the marine NMEA server.
Destination Port	Enter the number of the port to use to send NMEA data to the server.

To save the feature template, click Save.

## Release Information

Introduced in vManage NMS Release 18.1.1.

## IGMP

Use the IGMP template for all vEdge Cloud and vEdge router devices.

Internet Group Management Protocol (IGMP) allows vEdge routers to join multicast groups within a particular VPN.

To configure IGMP using vManage templates:


1. Create an IGMP feature template to configure IGMP parameters, as described in this article.
2. Create the interface in the VPN to use for IGMP. See the [VPN-Interface-Ethernet](#) help topic.
3. Create a VPN feature template to configure VPN parameters. See the [VPN](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Service VPN tab located directly beneath the Description field, or scroll to the Service VPN section.

Configuration

- Click the Service VPN drop-down.



- Under Additional VPN Templates, located to the right of the screen, click IGMP.
- From the IGMP drop-down, click Create Template. The IGMP template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining IGMP parameters.
- In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
- In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>

## Configuration

Global (indicated by a globe icon)	Enter a value for the parameter, and apply that value to all devices.  Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.
------------------------------------	--

## Configure IGMP

To configure IGMP, select the Basic Configuration tab to enable IGMP. Then, select the Interface tab and click Add New Interface to configure IGMP interfaces. All parameters listed below are required to configure IGMP.

Parameter Name	Description
Shutdown	Ensure that No is selected to enable IGMP.
Interface Name	Enter the name of the interface to use for IGMP.  To add another interface, click the plus sign (+). To delete an interface, click the trash icon to the right of the entry.
Join Group Address	Click Add Join Group Address, and enter the address of a multicast group for the interface to join.  Click Add to add the new interface

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
router
  igmp
    interface interface-name
      join-group group-address
    [no] shutdown
```

## Release Information


Introduced in vManage NMS in Release 15.2.

## Logging

Use the Logging template for all Viptela devices to configure logging to either the local hard drive or a remote host.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. To create a custom template for Logging, select the Factory\_Default\_Logging\_Template and click Create Template. The Logging template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining Logging parameters. You may need to click a tab or the plus sign (+) to display additional fields.



6. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
7. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Minimum Logging Configuration

The following logging parameters are configured by default on all Viptela devices:

- Log event notification system log (syslog) messages are logged to a file on the local device's hard disk, at a priority level of "information."
- Log files are placed in the directory /var/log on the local device.
- Log files are readable by the "admin" user.

## Configure Logging to the Local Disk

To configure logging of event notification system log messages to the local device's hard disk, select the Disk tab and configure the following parameters:

Parameter Name	Description
Enable Disk	Click On to allow syslog messages to be saved in a file on the local hard disk, or click Off to disallow it. By default, logging to a local disk file is enabled on all Viptela devices.
Maximum File Size	Enter the maximum size of syslog files. Syslog files are rotated on an hourly basis based on the file's size. When the file size exceeds configured value, the file is rotated and the syslogd process is notified. <i>Range:</i> 1 through 20 MB <i>Default:</i> 10 MB
Rotations	Enter the number of syslog files to create before discarding the oldest files. <i>Range:</i> 1 through 10 <i>Default:</i> 10
Priority	Select the priority level of the syslog message to save to the log files. The severity indicates the seriousness of the event that generated the message. The default priority value is "informational", so, by default, all syslog messages are recorded. The priority level can be one of the following (in order of decreasing severity): <ul style="list-style-type: none"> <li>• Emergency—System is unusable (corresponds to syslog severity 0).</li> <li>• Alert— Action must be taken immediately (corresponds to syslog severity 1).</li> <li>• Critical—Critical: A serious condition (corresponds to syslog severity 2).</li> <li>• Error—An error condition that does not fully impair system usability (corresponds to syslog severity 3).</li> <li>• Warning—A minor error condition (corresponds to syslog severity 4).</li> <li>• Notice—A normal, but significant condition (corresponds to syslog severity 5).</li> <li>• Informational—Routine condition (the default) (corresponds to syslog severity 6).</li> </ul>

To save the feature template, click Save.

*CLI equivalent:*

```
system
 logging
  disk
    enable
    file
      rotate number
      size megabytes
    priority priority
```

## Configure Logging to Remote Servers

To configure logging of event notification system log messages to a remote server, click the Server tab. Then click Add New Server and configure the following parameters:

Parameter Name	Description
Hostname/IP Address	Enter the DNS name, hostname, or IP address of the system on which to store syslog messages.  To add another syslog server, click the plus sign (+). To delete a syslog server, click the trash icon to the right of the entry.
VPN ID	Enter the identifier of the VPN in which the syslog server is located or through which the syslog server can be reached. <i>Range:</i> 0 through 65530
Source Interface	Enter the specific interface to use for outgoing system log messages. The interface must be located in the same VPN as the syslog server. Otherwise, the configuration is ignored. If you configure multiple syslog servers, the source interface must be the same for all of them.
Priority	Select the severity of the syslog message to save. The severity indicates the seriousness of the event that generated the message. <i>priority</i> can be one of the following: <ul style="list-style-type: none"> <li>• Emergency—System is unusable (corresponds to syslog severity 0).</li> <li>• Alert— Action must be taken immediately (corresponds to syslog severity 1).</li> <li>• Critical—Critical: A serious condition (corresponds to syslog severity 2).</li> <li>• Error—An error condition that does not fully impair system usability (corresponds to syslog severity 3).</li> <li>• Warning—A minor error condition (corresponds to syslog severity 4).</li> <li>• Notice—A normal, but significant condition (corresponds to syslog severity 5).</li> <li>• Informational—Routine condition (the default) (corresponds to syslog severity 6).</li> </ul> Click Add to save the logging server.

To edit a logging server, click the pencil icon to the right of the entry.

To remove a logging server, click the trash icon to the right of the entry.

To save the feature template, click Save.

*CLI equivalent:*

```

system
 logging
  server (dns-name | hostname | ip-address)
    priority priority
    source-interface interface-name
    vpn vpn-id

```

## Release Information

Introduced in vManage NMS in Release 15.2.

## Multicast

Use the Multicast template for all vEdge Cloud and vEdge router devices.

To configure a vEdge router to be a multicast replicator using vManage templates:


1. Create a multicast feature template to configure multicast replicator parameters, as described in this article.
2. Create a PIM feature template to enable PIM on each VPN that participates in a multicast domain. See the [PIM](#) help topic.
3. Create a VPN feature template to configure parameters for the VPN that is running PIM. See the [VPN](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.

Configuration

2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Service VPN tab located directly beneath the Description field, or scroll to the Service VPN section.
6. Click the Service VPN drop-down.



7. Under Additional VPN Templates, located to the right of the screen, click Multicast.
8. From the Multicast drop-down, click Create Template. The Multicast template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining Multicast parameters.
9. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
10. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
-----------------	-------------------



Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure a Multicast Replicator

To configure a vEdge router to be a multicast replicator, in the Basic Configuration tab, configure the following parameters:

Parameter Name	Description
Local	Click On to configure the local router as a multicast replicator.
Threshold	Specify the number of joins per group that the router can accept. For each join, the router can accept 256 outgoing tunnel interfaces (OILs). <i>Range:</i> 0 through 1000 <i>Default:</i> 0. A value of 0 means that the router can accept any number of (*,G) and (S,G) joins.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
router
  multicast-replicator local [threshold number]
```

## Release Information

Introduced in vManage NMS in Release 15.2.

## NTP

Use the NTP template for all Viptela devices.

Configure network time protocol (NTP) servers on your Viptela devices in order to synchronize time across all devices in the Viptela overlay network. You can configure up to four NTP servers, and they must all be located or reachable in the same VPN.


Other devices are allowed to ask a Viptela device for the time, but no devices are allowed to use the Viptela device as an NTP server.

To configure NTP using vManage templates:

1. Create an NTP feature template to configure NTP parameters, as described in this article.
2. Configure the timezone in the System template. See the [System](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Select the Basic Information tab.
6. Under Additional System Templates, located to the right of the screen, click NTP.



7. From the NTP drop-down, click Create Template. The NTP template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining NTP parameters.
8. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
9. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
-----------------	-------------------

Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure NTP Servers

To configure NTP servers, select the Server tab and click Add New Server. Then configure the following parameters. Parameters marked with an asterisk are required to configure NTP.

Parameter Name	Description
Hostname/IP Address*	Enter the IP address of an NTP server or of a DNS server that knows how to reach the NTP server.
Authentication Key*	Specify the MD5 key associated with the NTP server, to enable MD5 authentication. For the key to work, you must mark it as trusted in the Trusted Keys field, under the Authentication tab (discussed below).
VPN ID*	Enter the number of the VPN to use to reach the NTP server or the VPN in which the NTP server is located. If you configure multiple NTP servers, they must all be located or reachable in the same VPN.  <i>Range: 0 through 65530</i>
Version*	Enter the version number of the NTP protocol software. <i>Range: 1 through 4</i> <i>Default: 4</i>
Source Interface	Enter the name of a specific interface to use for outgoing NTP packets. The interface must be located in the same VPN as the NTP server. If it is not, the configuration is ignored.
Prefer	Click On if multiple NTP servers are at the same stratum level and you want one to be preferred. For servers at different stratum levels, the software chooses the one with the highest stratum level.

To add the NTP server, click Add.

To add another NTP server, click Add New Server. You can configure up to four NTP servers. The Viptela software uses the server at the highest stratum level.

To edit an NTP server, click the pencil icon to the right of the entry.

To delete an NTP server, click the trash icon to the right of the entry.

To save the feature template, click Save.

*CLI equivalent:*

```
system
 ntp
```

## Configuration

```

server (dns-server-address | ip-address)
  key key-id
  prefer
  source-interface interface-name
  version number
  vpn vpn-id

```

## Configure NTP Authentication

To configure authentication keys used to authenticate NTP servers, in the Authentication tab, click the Authentication Key tab. Then click Add New Authentication Key, and configure the following parameters. Parameters marked with an asterisk are required to configure NTP.

Parameter Name	Description
Authentication Key*	Select the following values: <ul style="list-style-type: none"> <li>Authentication Key—Enter an MD5 key ID. It can be a number from 1 through 65535.</li> <li>Authentication Value—Enter either a cleartext key or an AES-encrypted key.</li> </ul>
Authentication Value*	Enter an MD5 authentication key. For the key to be used, you must designate it as trusted. To associate a key with a server, enter the same value as you use for the the Authentication Key field on the Server tab.

To configure trusted keys used to authenticate NTP servers, in the Authentication tab, click the Trusted Keys tab and configure the following parameters;

Parameter Name	Description
Trusted Keys*	Enter the MD5 authentication key to designate the key as trustworthy. To associate this key with a server, enter the same value as you use for the the Authentication Key field on the Server tab.

*CLI equivalent:*

```

system
  ntp
    keys
      authentication key-id md5 md5-key
      trusted key-id

```

## Release Information

Introduced in vManage NMS in Release 15.2.

## OMP

Use the OMP template to configure OMP parameters for all vEdge Cloud and vEdge router devices, and for vSmart controllers.

The Viptela Overlay Management Protocol (OMP) establishes and maintains the Viptela control plane.


OMP is enabled by default on all vEdge routers, vManage NMSs, and vSmart controllers, so there is no need to explicitly configure or enable OMP. OMP must be operational for the Viptela overlay network to function. If you disable it, you disable the overlay network.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.

Configuration

3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. To create a custom template for OMP, select the Factory\_Default\_OMP\_Template and click Create Template. The OMP template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining OMP parameters. You may need to click a tab or the plus sign (+) to display additional fields.
6. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.



7. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>

Global (indicated by a globe icon)	Enter a value for the parameter, and apply that value to all devices.  Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.
------------------------------------	--

## Configure Basic OMP Options

To configure basic OMP options, select the Basic Configuration tab and configure the following parameters. All parameters are optional.

Parameter Name	Description
Graceful Restart for OMP	Ensure that Yes is selected to enable graceful restart. By default, graceful restart for OMP is enabled.
Overlay AS Number (on vEdge routers only)	Specify a BGP AS number that OMP advertises to the router's BGP neighbors.
Graceful Restart Timer	Specify how often the OMP information cache is flushed and refreshed. A timer value of 0 disables OMP graceful restart. <i>Range:</i> 0 through 604800 seconds (168 hours, or 7 days) <i>Default:</i> 43200 seconds (12 hours)
Number of Paths Advertised per Prefix	Specify the maximum number of equal-cost routes to advertise per prefix. vEdge routers advertise routes to vSmart controllers, and the controllers redistributes the learned routes, advertising each route-TLOC tuple. A vEdge router can have up to four TLOCs, and by default advertises each route-TLOC tuple to the vSmart controller. If a local site has two vEdge routers, a vSmart controller could potentially learn eight route-TLOC tuples for the same route. If the configured limit is lower than the number of route-TLOC tuples, the best route or routes are advertised. <i>Range:</i> 1 through 16 <i>Default:</i> 4
ECMP Limit (on vEdge routers only)	Specify the maximum number of OMP paths received from the vSmart controller that can be installed in the vEdge router's local route table. By default, a vEdge router installs a maximum of four unique OMP paths into its route table. <i>Range:</i> 1 through 32 <i>Default:</i> 4
Send Backup Paths (on vSmart Controllers only)	Click On to have OMP advertise backup routes to vEdge routers. By default, OMP advertises only the best route or routes. If you configure to send backup paths, OMP also advertises the first non-best route in addition to the best route or routes.
Shutdown	Ensure that No is selected, to enable to Viptela overlay network. Click Yes to disable OMP and disable the Viptela overlay network. OMP is enabled by default.
Discard rejected (on vSmart controllers only)	Click Yes to have OMP discard routes that have been rejected on the basis of policy. By default, rejected routes are not discarded.

To save the feature template, click Save.

### CLI equivalent:

```
omp
discard-rejected (on vSmart controllers only)
ecmp-limit number (on vEdge routers only)
graceful-restart
overlay-as as-number (on vEdge routers only)
send-backup-paths (on vSmart controllers only)
send-path-limit number
[no] shutdown
```

## Configure OMP Timers

To configure OMP timers, select the Timers tab and configure the following parameters:

Parameter Name	Description
Advertisement Interval	Specify the time between OMP Update packets. <i>Range:</i> 0 through 65535 seconds <i>Default:</i> 1 second
Hold Time	Specify how long to wait before closing the OMP connection to a peer. If the peer does not receive three consecutive keepalive messages within the hold time, the OMP connection to the peer is closed. <i>Range:</i> 0 through 65535 seconds <i>Default:</i> 60 seconds
EOR Timer	Specify how long to wait after an OMP session has gone down and then come back up to send an end-of-RIB (EOR) marker. After this marker is sent, any routes that were not refreshed after the OMP session came back up are considered to be stale and are deleted from the route table. <i>Range:</i> 1 through 3600 seconds (1 hour) <i>Default:</i> 300 seconds (5 minutes)

To save the feature template, click Save.

*CLI equivalent:*

```
omp
 timers
  advertisement-interval seconds
  graceful-restart-timer seconds
  holdtime seconds
```

## Configure OMP Advertisements

To advertise routes learned locally by the vEdge router to OMP, select the Advertise tab and configure the following parameters:

Parameter Name	Description
Advertise (on vEdge routers only)	Click On or Off to enable or disable the vEdge router advertising to OMP the routes that it learns locally: <ul style="list-style-type: none"> <li>BGP—Click On to advertise BGP routes to OMP. By default, BGP routes are not advertised to OMP.</li> <li>OSPF—Click On and click On again in the External field that appears to advertise external OSPF routes to OMP. OSPF inter-area and intra-area routes are always advertised to OMP. By default, external OSPF routes are not advertised to OMP.</li> <li>Connected—Click Off to disable advertising connected routes to OMP. By default, connected routes are advertised to OMP.</li> <li>Static—Click Off to disable advertising static routes to OMP. By default static routes are advertised to OMP.</li> </ul> <p>To configure per-VPN route advertisements to OMP, use the <a href="#">VPN feature template</a>.</p>

To save the feature template, click Save.

*CLI equivalent:*

```
omp
 advertise (bgp | connected | ospf | static) (on vEdge routers only)
```

## Release Information

Introduced in vManage NMS in Release 15.2.  
In Release 17.1, add Overlay AS Number field.

## OSPF

Use the OSPF template for all vEdge Cloud and vEdge router devices.


To configure OSPF on vEdge routers using vManage templates:

1. Create an OSPF feature template to configure OSPF parameters, as described in this article. OSPF can be used for service-side routing, to provide reachability to networks at the local site, and it can be used for transport-side routing, to enable communication between the vEdge router and other Viptela devices when the router is not directly connected to the WAN cloud. Create separate OSPF templates for the two OSPF routing types.
2. Create a VPN feature template to configure VPN parameters for either service-side OSPF routing (in any VPN other than VPN 0 or VPN 512) or transport-side OSPF routing (in VPN 0). See the [VPN](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. To create a template for VPN 0 or VPN 512:
  - a. Click the Transport & Management VPN tab located directly beneath the Description field, or scroll to the Transport & Management VPN section.
  - b. Under Additional VPN 0 Templates, located to the right of the screen, click OSPF.
  - c. From the OSPF drop-down, click Create Template. The OSPF template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining OSPF parameters.
6. To create a template for VPNs 1 through 511, and 513 through 65530:
  - a. Click the Service VPN tab located directly beneath the Description field, or scroll to the Service VPN section.
  - b. Click the Service VPN drop-down.
  - c. Under Additional VPN Templates, located to the right of the screen, click OSPF.
  - d. From the OSPF drop-down, click Create Template. The OSPF template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining OSPF parameters.





7. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
8. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure Basic OSPF

To configure basic OSPF, select the Basic Configuration tab and then configure the following parameters. All these parameters are optional. For OSPF to function, you must configure area 0, as described below.

Parameter Name	Description
Router ID	Enter the OSPF router ID, in decimal four-part dotted notation. This is the IP address associated with the router for OSPF adjacencies.
Distance for External Routes	Specify the OSPF route administration distance for routes learned from other domains.  <i>Range:</i> 0 through 255 <i>Default:</i> 110
Distance for Inter-Area Routes	Specify the OSPF route administration distance for routes coming from one area into another.  <i>Range:</i> 0 through 255 <i>Default:</i> 110
Distance for intra-Area routes	Specify the OSPF route administration distance for routes within an area.  <i>Range:</i> 0 through 255 <i>Default:</i> 110

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
router
  distance
    external number
    inter-area number
    intra-area number
  router-id
```

## Redistribute Routes into OSPF

To redistribute routes learned from other protocols into OSPF on vEdge routers, select the Redistribute tab. Click Add New Redistribute and configure the following parameters:

Parameter Name	Description
Protocol	Select the protocol from which to redistribute routes into OSPF. Select from BGP, Connected, NAT, OMP, and Static.
Route Policy	Enter the name of a localized control policy to apply to routes before they are redistributed into OSPF.

To add another OSPF route redistribution policy, click the plus sign (+).

To remove an OSPF route redistribution policy from the template configuration, click the trash icon to the right of the entry.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
router
  ospf
    redistribute (bgp | connected | nat | omp | static) route-policy policy-name
```

## Configure OSPF To Advertise a Maximum Metric

To configure OSPF to advertise a maximum metric so that other routers do not prefer this vEdge router as an intermediate hop in their Shortest Path First (SPF) calculation, select the Maximum Metric (Router LSA) tab. Then click Add New Router LSA and configure the following parameters:

Parameter Name	Description
Type	Select a type: <ul style="list-style-type: none"> <li>Administrative—Force the maximum metric to take effect immediately, through operator intervention.</li> <li>On-Startup—Advertise the maximum metric for the specified time.</li> </ul>
Advertisement Time	If you selected On-Startup, specify the number of seconds to advertise the maximum metric after the router starts up.  <i>Range:</i> 0, 5 through 86400 seconds <i>Default:</i> 0 seconds (the maximum metric is advertised immediately when the router starts up)

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  router
    ospf
      max-metric
        router-lsa (administrative | on-startup seconds)
```

## Configure OSPF Areas

To configure an OSPF area within a VPN on a vEdge router, select the Area tab and click Add New Area. For OSPF to function, you must configure area 0.

Parameter Name	Description
Area Number	Enter the number of the OSPF area.  <i>Range:</i> 32-bit number
Set the Area Type	Select the type of OSPF area, Stub or NSSA.
No Summary	Select On to not inject OSPF summary routes into the area.
Translate	If you configured the area type as NSSA, select when to allow vEdge routers that are ABRs (area border routers) to translate Type 7 LSAs to Type 5 LSAs:  always—Router always acts as the translator for Type 7 LSAs. That is, no other router, even if it is an ABR, can be the translator. If two ABRs are configured to always be the translator, only one of them actually ends up doing the translation. candidate—Router offers translation services, but does not insist on being the translator. never—Translate no Type 7 LSAs

To save the new area, click Add.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  router
    ospf
```

## Configuration

```

area number
  nssa
    no-summary
    translate (always | candidate | never)
  stub
    no-summary

```

## Configure Interfaces in an OSPF Area

To configure the properties of an interface in an OSPF area, select the Area tab and click Add New Area. Then, in Interface, click Add Interface. In the Add Interface popup, configure the following parameters:

Parameter Name	Description
Interface Name	Enter the name of the interface, in the format <b>ge slot / port</b> or <b>loopback number</b> .
Hello Interval	Specify how often the router sends OSPF hello packets.  <i>Range:</i> 1 through 65535 seconds <i>Default:</i> 10 seconds
Dead Interval	Specify how often the vEdge router must receive an OSPF hello packet from its neighbor. If no packet is received, the vEdge router assumes that the neighbor is down.  <i>Range:</i> 1 through 65535 seconds <i>Default:</i> 40 seconds (4 times the default hello interval)
LSA Retransmission Interval	Specify how often the OSPF protocol retransmits LSAs to its neighbors.  <i>Range:</i> 1 through 65535 seconds <i>Default:</i> 5 seconds
Interface Cost	Specify the cost of the OSPF interface.  <i>Range:</i> 1 through 65535

To configure advanced options for an interface in an OSPF area, in the Add Interface popup, click Advanced Options and configure the following parameters:

Parameter Name	Description
Designated Router Priority	Set the priority of the router to be elected as the designated router (DR). The router with the highest priority becomes the DR. If the priorities are equal, the node with the highest router ID becomes the DR or the backup DR. <i>Range:</i> 0 through 255 <i>Default:</i> 1
OSPF Network Type	Select the OSPF network type to which the interface is to connect: <ul style="list-style-type: none"> <li>Broadcast network—WAN or similar network.</li> <li>Point-to-point network—Interface connects to a single remote OSPF router.</li> </ul> <i>Default:</i> Broadcast
Passive Interface	Select On or Off to specify whether to set the OSPF interface to be passive. A passive interface advertises its address, but does not actively run the OSPF protocol. <i>Default:</i> Off
Authentication	Specify the authentication and authentication key on the interface, to allow OSPF to exchange routing update information securely:

## Configuration

• Authentication Type	Select the authentication type: <ul style="list-style-type: none"> <li>• Simple authentication—Password is sent in clear text.</li> <li>• Message-digest authentication—MD5 algorithm generates the password.</li> </ul>
• Authentication Key	Enter the authentication key. Plain text authentication is used when devices within an area cannot support the more secure MD5 authentication. The key can be 1 to 32 characters.
Message Digest	Specify the key ID and authentication key if you are using message digest (MD5):
• Message Digest Key ID	Enter the key ID for message digest (MD5 authentication). It can be 1 to 32 characters.
• Message Digest Key	Enter the MD5 authentication key, in clear text or as an AES-encrypted key. It can be from 1 to 255 characters.

To save the interface configuration, click Save.

To save the new area, click Add.

To save the feature template, click Save.

*CLI equivalent:*

```

vpn vpn-id
  router
    ospf
      area number
        interface interface-name
          authentication
            authentication-key key
            message-digest key
            type (message-digest | simple)
          cost number
          dead-interval seconds
          hello-interval seconds
          network (broadcast | point-to-point)
          passive-interface
          priority number
          retransmit-interval seconds

```

## Configure an Interface Range for Summary LSAs

To configure the properties of an interface in an OSPF area, select the Area tab and click Add New Area. Then, in Range, click Add Range. In the Area Range popup, click Add Area Range and configure the following parameters:

Parameter Name	Description
Address	Enter the IP address and subnet mask, in the format <i>prefix / length</i> , for the IP addresses to be consolidated and advertised.
Cost	Specify a number for the Type 3 summary LSA. OSPF uses this metric during its SPF calculation to determine the shortest path to a destination. <i>Range:</i> 0 through 16777215
No Advertise	Select On to not advertise the Type 3 summary LSAs or Off to advertise them.

To save the area range, click Save.

To save the new area, click Add.

## Configuration

To save the feature template, click Save.

**CLI equivalent:**

```
vpn vpn-id
router
  ospf
    area number
      range prefix/length
      cost number
      no-advertise
```

## Configure Other OSPF Properties

To configure other OSPF properties, select the Advanced tab and configure the following properties:

Parameter Name	Description
Reference Bandwidth	Specify the reference bandwidth for the OSPF auto-cost calculation for the interface.  <i>Range:</i> 1 through 4294967 Mbps <i>Default:</i> 100 Mbps
RFC 1538 Compatible	By default, the OSPF calculation is done per RFC 1583. Select Off to calculate the cost of summary routes based on RFC 2328.
Originate	Click On to generate a default external route into an OSPF routing domain: <ul style="list-style-type: none"> <li>Always—Select On to always advertise the default route in an OSPF routing domain.</li> <li>Default metric—Set the metric used to generate the default route. <i>Range:</i> 0 through 16777214 <i>Default:</i> 10</li> <li>Metric type—Select to advertise the default route as an OSPF Type 1 external route or an OSPF Type 2 external route.</li> </ul>
SPF Calculation Delay	Specify the amount of time between when the first change to a topology is received until performing the SPF calculation.  <i>Range :</i> 0 through 600000 milliseconds (60 seconds) <i>Default :</i> 200 milliseconds
Initial Hold Time	Specify the amount of time between consecutive SPF calculations.  <i>Range :</i> 0 through 600000 milliseconds (60 seconds) <i>Default :</i> 1000 milliseconds
Maximum Hold Time	Specify the longest time between consecutive SPF calculations.  <i>Range :</i> 0 through 600000 <i>Default :</i> 10000 milliseconds (60 seconds)
Policy Name	Enter the name of a localized control policy to apply to routes coming from OSPF neighbors.

To save the feature template, click Save.

**CLI equivalent:**

```
vpn vpn-id
router
  ospf
```

## Configuration

```
auto-cost reference-bandwidth mbps
compatible rfc1583
default-information
  originate (always | metric metric | metric-type type)
route-policy policy-name in
timers
  spf delay initial-hold-time maximum-hold-time
```

## Release Information

Introduced in vManage NMS in Release 15.2.

## PIM

Use the PIM template for all vEdge Cloud and vEdge router devices.


To configure the PIM Sparse Mode (PIM-SM) protocol using vManage templates so that a router can participate in the Viptela multicast overlay network:

1. Create a PIM feature template to configure PIM parameters, as described in this article.
2. Optionally, create an IGMP feature template to allow individual hosts on the service side to join multicast groups within a particular VPN. See the [IGMP](#) help topic.
3. Optionally, create a Multicast feature template to configure a vEdge router to be a multicast replicator. See the [Multicast](#) help topic.
4. Create a VPN feature template to configure parameters for the VPN that is running PIM. See the [VPN](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Service VPN tab located directly beneath the Description field, or scroll to the Service VPN section.

- Click the Service VPN drop-down.



- Under Additional VPN Templates, located to the right of the screen, click PIM.
- From the PIM drop-down, click Create Template. The PIM template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining PIM parameters.
- In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
- In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>



## Configuration

Global (indicated by a globe icon)	Enter a value for the parameter, and apply that value to all devices.  Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.
------------------------------------	--

## Configure Basic PIM

To configure PIM, select the Basic Configuration tab and configure the following parameters. Parameters marked with an asterisk are required to configure PIM.

Parameter Name	Description
Shutdown*	Ensure that No is selected, to enable PIM.
Auto-RP	Click On to enable auto-RP to enable automatic discovery of rendezvous points (RPs) in the PIM network so that the router receives a group-to-RP mapping updates. By default, auto-RP is disabled.
SPT Threshold	Specify the traffic rate, in kbps, at which to switch from the shared tree to the shortest-path tree (SPT). Configuring this value forces traffic to remain on the shared tree and travel via the RP instead of via the SPT.
Replicator	For a topology that includes multicast replicators, determine how the replicator for a multicast group is chosen: <ul style="list-style-type: none"> <li>Random—Choose the replicator at random.</li> <li>Sticky—Always use the same replicator. This is the default.</li> </ul>

To save the feature template, click Save.

### CLI equivalent:

```
vpn vpn-id
router
  pim
    auto-rp
    replicator-selection
    [no] shutdown
    spt-threshold kbps
```

## Configure PIM Interfaces

If the router is just a multicast replicator and is not part of a local network that contains either multicast sources or receivers, you do not need to configure any PIM interfaces. The replicator learns the locations of multicast sources and receivers from the OMP messages it exchanges with the vSmart controller. These control plane messages are exchanged in the transport VPN (VPN 0). Similarly, other vEdge routers discover replicators dynamically, through OMP messages from the vSmart controller.

To configure PIM interfaces, select the Interface tab. Then click Add New Interface and configure the following parameters:

Parameter Name	Description
Name	Enter the name of an interface that participates in the PIM domain, in the format <b>ge slot /port</b> .
Hello Interval	Specify how often the interface sends PIM hello messages. Hello messages advertise that PIM is enabled on the router. <i>Range:</i> 1 through 3600 seconds <i>Default:</i> 30 seconds

Join/Prune Interval	Specify how often PIM multicast traffic can join or be removed from a rendezvous point tree (RPT) or shortest-path tree (SPT). vEdge routers send join and prune messages to their upstream RPF neighbor. <i>Range:</i> 10 through 600 seconds <i>Default:</i> 60 seconds
---------------------	---

To edit an interface, click the pencil icon to the right of the entry.

To delete an interface, click the trash icon to the right of the entry.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
router
  pim
    interface interface-name
      hello-interval seconds
      join-prune-interval seconds
```

## Release Information


Introduced in vManage NMS in Release 15.2.

## Security

Use the Security template for all Viptela devices. On vEdge Cloud and vEdge routers and on vBond orchestrators, use this template to configure IPsec for data plane security. On vManage NMSs and vSmart controllers, use this template to configure DTLS or TLS for control plane security.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. To create a custom template for Security, select the Factory\_Default\_Security\_Template and click Create Template. The Security template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining Security parameters.
6. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.



7. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure Control Plane Security

To configure the control plane connection protocol on a vManage NMS or a vSmart controller, select the Basic Configuration tab and configure the following parameters:

Parameter Name	Description
Protocol	Select the protocol to use on control plane connections to a vSmart controller: <ul style="list-style-type: none"> <li>DTLS (Datagram Transport Layer Security). This is the default.</li> <li>TLS (Transport Layer Security)</li> </ul>
Control TLS Port	If you selected TLS, configure the port number to use: <i>Range:</i> 1025 through 65535 <i>Default:</i> 23456

To save the feature template, click Save

*CLI equivalent:*

```
security
 control
  protocol (dtls | tls)
  tls-port port-number
```

## Configure Data Plane Security

To configure data plane security on a vBond controller or vEdge router, select the Basic Configuration and Authentication Type tabs, and configure the following parameters:

Parameter Name	Description
Rekey Time	Specify how often a vEdge router changes the AES key used on its secure DTLS connection to the vSmart controller. If OMP graceful restart is enabled, the rekeying time must be at least twice the value of the OMP graceful restart timer. <i>Range:</i> 10 through 1209600 seconds (14 days) <i>Default:</i> 86400 seconds (24 hours)
Replay Window	Specify the size of the sliding replay window. <i>Values:</i> 64, 128, 256, 512, 1024, 2048, 4096, 8192 packets <i>Default:</i> 512 packets
Authentication Type	Select the authentication types from the Authentication List, and click the arrow to move them to the Selected List: <ul style="list-style-type: none"> <li>ah-no-id—Enable a modified version of AH-SHA1 HMAC and ESP HMAC-SHA1 that ignores the ID field in the packet's outer IP header.</li> <li>ah-sha1-hmac—Enable AH-SHA1 HMAC and ESP HMAC-SHA1.</li> <li>none—Select no authentication.</li> <li>sha1-hmac—Enable ESP HMAC-SHA1.</li> </ul>

To save the feature template, click Save.

*CLI equivalent:*

```
security
 ipsec
  authentication-type type
```

## Configuration

```
rekey seconds
replay-window number
```

## Release Information

Introduced in vManage NMS in Release 15.2.

## SNMP

Use the SNMP template to configure SNMP parameters for all Viptela devices and Cisco IOS XE routers running the SD-WAN software.

Note: A single device template can contain only one SNMP feature template. So in a single device template you can configure either SNMPv2 or SNMPv3, but not both.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Additional Templates tab located directly beneath the Description field, or scroll to the Additional Templates section.
6. From the SNMP drop-down, click Create Template. The SNMP template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining SNMP parameters.

The screenshot displays the Cisco vManage interface for configuring an SNMP template. The left sidebar shows the navigation menu with 'Configuration' selected. The main content area is titled 'CONFIGURATION | TEMPLATES' and has tabs for 'Device' and 'Feature'. Under the 'Feature' tab, there is a breadcrumb 'Feature Template > Add Template > SNMP'. The form includes the following fields:

- Device Type:** vEdge Cloud
- Template Name:** A text input field.
- Description:** A text input field.
- SNMP Version:** A dropdown menu with 'SNMP' selected.
- SNMP Section:** Contains several configuration options:
  - Shutdown:** A radio button group with 'Yes' selected and 'No' unselected.
  - Name of Device for SNMP:** A dropdown menu.
  - Contact Person:** A dropdown menu.
  - Location of Device:** A dropdown menu.
- SNMP VERSION:** A section header for the next part of the form.

At the bottom of the form, there are 'Save' and 'Cancel' buttons. The user's name 'admin' is visible in the top right corner of the interface.

## Configuration

7. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
8. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configuring Basic SNMP

To configure basic SNMP, select the SNMP tab and configure the following parameters. All parameters are required.

Parameter Name	Description
Shutdown	Click No to enable SNMP. By default, SNMP is disabled.
Name of Device for SNMP	Enter a name for the Viptela device to identify it in SNMP notifications.
Contact Person	Enter the name of the network management contact person in charge of managing the Viptela device. It can be a maximum of 255 characters.
Location of Device	Enter a description of the location of the device. It can be a maximum of 255 characters.

To save the feature template, click Save.

*CLI equivalent:*

```
snmp
  contact string
  location string
  name string
  [no] shutdown
```

## Configure SNMPv2

To configure SNMPv2, select the SNMP Version tab and click V2. For SNMPv2, you can configure communities and trap information.

## Configuration

To configure SNMP views, in the View & Community section, select the View tab. Then click Add New View, and configure the following parameters:

Parameter Name	Description
Name	Enter a name for the view. A view specifies the MIB objects that the SNMP manager can access. The view name can be a maximum of 255 characters. You must add a view name for all views before adding a community.
Object Identifiers	<p>Click Add Object Identifiers and configure the following parameters:</p> <ul style="list-style-type: none"> <li>Exclude OID—Enter the OID of the object. For example, to view the Internet portion of the SNMP MIB, enter the OID 1.3.6.1. To view the private portion of the Viptela MIB, enter the OID 1.3.6.1.4.1.41916. Use the asterisk wildcard (*) in any position of the OID subtree to match any value at that position rather than matching a specific type or name.</li> <li>On/Odd—Click Off to include the OID in the view or click On to exclude the OID from the view.</li> </ul> <p>To save the object identifiers, click Save.</p> <p>To remove an OID from the list, click the minus sign to the right of the entry.</p>

To add the SNMP view, click Add.

To configure the SNMP community, select the Community tab. Then click Add New Community, and configure the following parameters:

Parameter Name	Description
Name	Enter the name for the community. The name can be from 1 through 32 characters and can include angle brackets (< and >).
Authorization	Select read-only from the dropdown list. The MIBs supported by the Viptela software do not allow write operations, so you can configure only read-only authorization.
View	Select a view to apply to the community. The view specifies the portion of the MIB tree the community can access.

To add the SNMP community, click Add.

To configure trap, in the Trap section, select the Trap Group tab. Then click Add New Trap Group, and configure the parameters below.

Note that an IOS XE router has no trap groups. As such, you must create a dummy trap group before you can configure the trap target server.

Parameter Name	Description
Group Name	Enter a name for the trap group. It can be from 1 to 32 characters long.

Trap Type Modules	<p>Click Add Trap Type Modules, and configure the following parameters:</p> <p>In Severity Levels, select one or more severity levels for the trap—critical, major, or minor.</p> <p>In Module Name, select the type of traps to include in the trap group:</p> <ul style="list-style-type: none"> <li>• all—All trap types.</li> <li>• app-route—Traps generated by application-aware routing.</li> <li>• bfd—Traps generated by BFD and BFD sessions.</li> <li>• control—Traps generated by DTLS and TLS sessions.</li> <li>• dhcp—Traps generated by DHCP.</li> <li>• hardware—Traps generated by Viptela hardware.</li> <li>• omp—Traps generated by OMP.</li> <li>• routing—Traps generated by BGP, OSPF, and PIM.</li> <li>• security—Trap generated by certificates, vSmart and vEdge serial number files, and IPsec.</li> <li>• system—Traps generated by system-wide functions.</li> <li>• vpn—Traps generated by VPN-specific functions, including interfaces and VRRP.</li> </ul>
-------------------	--

To save the trap type module, click Save.

To configure trap target servers, in the Trap section, select the Trap Target Server tab. Then click Add New Trap Group, and configure the parameters below.

Note that on a vEdge router, you can bind a different source interface to each trap target server. On an IOS XE router, however, the last occurrence of the source interface is chosen as the global source interface.

Parameter Name	Description
VPN ID	Enter the number of the VPN to use to reach the trap server. <i>Range:</i> 0 through 65530
IP Address	Enter the IP address of the SNMP server.
UDP Port	Enter the UDP port number for connecting to the SNMP server. <i>Range:</i> 1 though 65535
Group Name	Select the name of a trap group that was configured under the Group tab.
Community Name	Select the name of a community that was configured under the Community tab.
Source Interface	Enter the interface to use to send traps to the SNMP server that is receiving the trap information.

To save the trap target, click Add

To save the feature template, click Save.

*CLI equivalent:*

```
snmp
  community name
    authorization (read-only | read-write)
  view string
  trap
    group group-name
```



## Configuration

```

trap-type
  level severity
target vpn vpn-id ip-address udp-port
  community-name community-name
  group-name name
view string
oid oid-number [exclude]

```

## Configure SNMPv3

To configure SNMPv3, in **SNMP Version**, click **V3**. For SNMPv3, you can configure groups, users, and trap information. Configure groups and trap information as described above.

To configure SNMPv3 users, in the **User** section, click **Add New User** and enter the following parameters:

Parameter Name	Description
User	Enter a name of the SNMP user. It can be 1 to 32 alphanumeric characters.
Authentication Protocol	Select the authentication mechanism for the user: <ul style="list-style-type: none"> <li>MD5—Use message digest 5.</li> <li>SHA—Use SHA-2 message digest.</li> </ul>
Authentication Password	Enter the authentication password either in cleartext or as an AES-encrypted key.
Privacy Protocol	Select the privacy type for the user: <ul style="list-style-type: none"> <li>AES-CFB-128—Use Advanced Encryption Standard cipher algorithm used in cipher feedback mode, with a 128-bit key.</li> </ul>
Privacy Password	Enter the authentication password either in cleartext or as an AES-encrypted key.
Group	Select the name of a configure SNMPv3 group.

To save the user, click **Add**.

To save the feature template, click **Save**.

*CLI equivalent:*

```

snmp
group group-name authentication
  view string
trap
  group group-name
  trap-type
  level severity
target vpn vpn-id ip-address udp-port
  community-name community-name
  group-name name
user username
  auth authentication
  auth-password password
  group group-name
  priv privacy
  priv-password password

```

## Release Information

Introduced in vManage NMS in Release 15.2.

In Release 16.2, add support for SNMPv3.

In Release 17.2, remove support for DES privacy for the SNMP user.

## Switch Port

Use the Switch Port template for Cisco IOS XE routers.


To have a vEdge router act as a transparent bridge, configure bridging domains on the router. A router can have up to 16 bridging domains.

To configure the switch ports using vManage templates:

1. Create a Switch Port feature template, as described in this article.
2. To use the switch port for routing, associate it with an SVI. See the [VPN Interface SVI](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Additional Templates tab located directly beneath the Description field, or scroll to the Additional Templates section.
6. Click the plus sign (+) next to Switch Port.
7. In the Switch Port drop-down, select the port number.
8. From the lower Switch Port drop-down, click Create Template. The Switch Port template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining switch port parameters.



9. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
10. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure Basic Switch Port Parameters

To configure basic switch port parameters, select the Basic Configuration tab and configure the following parameters:

Parameter Name	Description
Slot	Enter the number of the slot in which the Layer 2 switch port module is installed.
Module	Select the switch port module type, either 4 port or 8 port.

To save the feature template, click Save.

## Associate Interfaces with the Switch Port

To associate an interface with the switch port, click the Interface tab and click Add New Interface:

Parameter Name	Description
Interface Name	Enter the name of the interface to associate with the bridging domain, in the format <b>ge slot / port</b> .
Shutdown	Click No to enable the interface. By default, an interface is disabled.
Switch Port	<p>Select the switch port mode:</p> <ul style="list-style-type: none"> <li>• Access—Configure the interface as an access port. You can configure only one VLAN on an access port, and the port can carry traffic for only one VLAN. <ul style="list-style-type: none"> <li>– VLAN Name—Enter a description for the VLAN.</li> <li>– VLAN ID—Enter the VLAN number, which can be a value from 1 through 4094.</li> </ul> </li> <li>• Trunk—Configure the interface as a trunk port. You can configure one or more VLANs on a trunk port, and the port can carry traffic for multiple VLAN. <ul style="list-style-type: none"> <li>– Allowed VLANs—Enter the numbers of the VLANs for which the trunk can carry traffic.a description for the VLAN.</li> <li>– Native VLAN ID—Enter the number of the VLAN allowed to carry untagged traffic.</li> </ul> </li> </ul>

To save the feature template, click Save.

## Configure Other Interface Properties

To configure other interface properties, select the Advanced tab and configure the following properties:

Parameter Name	Description
Age-Out Time	Enter how long an entry is in the MAC table before it ages out. Set the value to 0 to prevent entries from timing out. <i>Range:</i> 0, 10 through 1000000 seconds <i>Default:</i> 300 seconds

Static MAC Address	<p>Click Add Static MAC Address to map a MAC address to a switch port. In the MAC Static Address field that appears, enter the following:</p> <ul style="list-style-type: none"> <li>• MAC Address—Enter the static MAC address to map to the switch port interface.</li> <li>• Switch Port Interface Name—Enter the name of the switch port interface.</li> <li>• VLAN ID—Enter the number of the VLAN for the switch port.</li> </ul> <p>Click Add to save the static MAD access mapping.</p>
--------------------	---

To save the feature template, click Save.

## Release Information

Introduced in vManage NMS in Release 18.3.

## System


Use the System template for all Viptela devices.

To configure system-wide parameters using vManage templates:

1. Create a System feature template to configure system parameters, as described in this article.
2. Create an NTP feature template to configure NTP servers and authentication. See the [NTP](#) help topic.
3. Configure the organization name and vBond orchestrator IP address on the vManage NMS. See the [Settings](#) help topic. These settings are appended to the device templates when the templates are pushed to devices.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. To create a custom template for System, select the Factory\_Default\_System\_Template and click Create Template. The System template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining System parameters.
6. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.



- In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Basic System-Wide Configuration

To set up system-wide functionality on a Viptela device, select the Basic Configuration tab and then configure the following parameters. Parameters marked with an asterisk are required.

Parameter Field	Description
Site ID* (on vEdge routers, vManage NMSs, and vSmart controllers)	Enter the identifier of the site in the Viptela overlay network domain in which the device resides, such as a branch, campus, or data center. The site ID must be the same for all Viptela devices that reside in the same site. <i>Range:</i> 1 through 4294967295 ( $2^{32} - 1$ )
System IP*	Enter the system IP address for the Viptela device, in decimal four-part dotted notation. The system IP address provides a fixed location of the device in the overlay network and is a component of the device's TLOC address. It is used as the device's loopback address in the transport VPN (VPN 0). You cannot use this same address for another interface in VPN 0.
Timezone*	Select the timezone to use on the device.
Hostname	Enter a name for the Viptela device. It can be up to 32 characters.
Location	Enter a description of the location of the device. It can be up to 128 characters.
Device Groups	Enter the names of one or more groups to which the device belongs, separated by commas.
Controller Groups (on vEdge routers only)	List the vSmart controller groups to which the vEdge router belongs.
Description	Enter any additional descriptive information about the device.
Console Baud Rate (vEdge routers only)	Select the baud rate of the console connection on the vEdge router. <i>Values:</i> 1200, 2400, 4800, 9600, 19200, 38400, 57600, 115200 baud or bits per second (bps) <i>Default:</i> 115200 bps
Maximum OMP Sessions (on vEdge routers only)	Set the maximum number of OMP sessions that a vEdge router can establish to a vSmart controller. <i>Range :</i> 0 through 100 <i>Default:</i> 2
Dedicated Core for TCP Optimization (optional, on vEdge 1000 and 2000 routers only)	Click on to carve out a separate CPU core to use for performing TCP optimization.

To save the feature template, click Save.

### CLI equivalent:

```
system
 clock
  timezone timezone
 console-baud-rate rate
 controller-group-list numbers
 description text
 device-groups group-name
 host-name string
 location string
 max-omp-sessions number
 site-id site-id
 system-ip ip-address
 tcp-optimization-enabled
```

To configure the DNS name or IP address of the vBond orchestrator in your overlay network, go to the **Administration ► Settings** screen and click vBond.

## Configure the GPS Location

To configure a device's location, select the GPS tab and then configure the following parameters. This location is used to place the device on the vManage NMS network map. Setting the location also allows the vManage NMS to send a notification if the device is moved to another location.

Parameter Field	Description
Latitude	Enter the latitude of the device, in the format <i>decimal-degrees</i> .
Longitude	Enter the longitude of the device, in the format <i>decimal-degrees</i> .

To save the feature template, click Save.

*CLI equivalent:*

```
system
  gps-location (latitude decimal-degrees | longitude decimal-degrees)
```

## Configure Interface Trackers

To Track the status of transport interfaces that connect to the internet, click the Tracker tab. Then click Add New Tracker and configure the following parameters:

Parameter Field	Description
Name	Name of the tracker. The name can be up to 128 alphanumeric characters. You can configure up to eight trackers.
Threshold	How long to wait for the probe to return a response before declaring that the transport interface is down. <i>Range:</i> 100 through 1000 milliseconds <i>Default:</i> 300 milliseconds
Interval	How often probes are sent to determine the status of the transport interface. <i>Range:</i> 10 through 600 seconds <i>Default:</i> 60 seconds (1 minute)
Multiplier	Number of times to resend probes before declaring that the transport interface is down. <i>Range:</i> 1 through 10 <i>Default:</i> 3
End Point Type: IP Address	IP address of the end point of the tunnel interface. This is the destination in the internet to which the router sends probes to determine the status of the transport interface. For each tracker, you must configure either one DNS name or one IP address.
End Point Type: DNS Name	DNS name of the end point of the tunnel interface. This is the destination in the internet to which the router sends probes to determine the status of the transport interface. For each tracker, you must configure either one DNS name or one IP address.

To save a tracker, click Add.

To save the feature template, click Save.

*CLI equivalent:*

```
system
  tracker tracker-name
    endpoint-dns-name dns-name
    endpoint-ip ip-address
    interval seconds
```



## Configuration

```
multiplier number
threshold milliseconds
```

To apply a tracker to an interface, configure it in the VPN Interface Cellular, VPN Interface Ethernet, VPN Interface NAT Pool, or VPN Interface PPP configuration template. You can apply only one tracker to an interface.

## Configure Advanced Options

To configure additional system parameters, click the Advanced tab:

Parameter Name	Description
Control Session Policer Rate	Specify a maximum rate of DTLS control session traffic, to police the flow of control traffic. <i>Range:</i> 1 through 65535 pps <i>Default:</i> 300 pps
MTU of DTLS Tunnel	Specify the MTU size to use on the DTLS tunnels that send control traffic between Viptela devices. <i>Range:</i> 500 through 2000 bytes <i>Default:</i> 1024 bytes
Port Hopping	Click On to enable port hopping, or click Off to disable it. When a Viptela device is behind a NAT, port hopping rotates through a pool of preselected OMP port numbers (called base ports) to establish DTLS connections with other Viptela devices when a connection attempt is unsuccessful. The default base ports are 12346, 12366, 12386, 12406, and 12426. To modify the base ports, set a port offset value. To disable port hopping on an individual TLOC (tunnel interface), use the <a href="#">VPN Interface Ethernet</a> configuration template. <i>Default:</i> Enabled (on vEdge routers); disabled (on vManage NMSs and vSmart controllers)
Port Offset	Enter a number by which to offset the base port number. Configure this option when multiple Viptela devices are behind a single NAT device, to ensure that each device uses a unique base port for DTLS connections. <i>Values:</i> 0 through 19
DNS Cache Timeout	Specify when to time out the vBond orchestrator addresses that have been cached by the device. <i>Range:</i> 1 through 30 minutes <i>Default:</i> 30 minutes
Track Transport	Click On to regularly check whether the DTLS connection between the device and a vBond orchestrator is up. Click Off to disable checking. By default, transport checking is enabled
Local vBond (only on vEdge routers acting as vBond orchestrators)	Click On to configure the vEdge router to act as a vBond orchestrator. Then specify the DNS name for the vBond orchestrator or its IP address, in decimal four-part dotted notation.
Track Interface (on vEdge routers only)	Set the tag string to include in routes associated with a network that is connected to a non-operational interface. <i>Range:</i> 1 through 4294967295
Multicast Buffer (on vEdge routers only)	Specify the percentage of interface bandwidth that multicast traffic can use. <i>Range:</i> 5% through 100% <i>Default:</i> 20%
USB Controller (on vEdge 1000 and 2000 series routers only)	Click On to enable or click Off to disable the USB controller, which drives the external USB ports. If you enable the USB controller, the vEdge router reboots when you attach the device template to the device. <i>Default:</i> Disabled
Gateway Tracking	Click On to enable or click Off to Disable tracking of default gateway. Gateway tracking determines, for static routes, whether the next hop is reachable before adding that route to the device's route table. <i>Default:</i> Enabled
Host Policer Rate (on vEdge routers only)	Specify the maximum rate at which a policer delivers packets to the control plane. <i>Range:</i> 1000 through 20000 pps <i>Default:</i> 5000 pps

ICMP Error Rate (on vEdge routers only)	Specify how many ICMP error messages a policer can generate or receive. <i>Range:</i> 1 through 200 pps <i>Default:</i> 100 pps
Allow Same-Site Tunnel (on vEdge routers only)	Click On to allow tunnels to be formed between vEdge routers in the same site. Note that no BFD sessions are established between the two collocated vEdge routers. <i>Default:</i> Off
Route Consistency Check (on vEdge routers only)	Click On to check whether the IPv4 routes in the device's route and forwarding table are consistent.
Collect Admin Tech on Reboot	Click On to collect admin-tech information when the device reboots.
Idle Timeout	Set how long the CLI is inactive on a device before the user is logged out. If a user is connected to the device via an SSH connection, the SSH connection is closed after this time expires. <i>Range:</i> 0 through 300 seconds <i>Default:</i> CLI session does not time out
Eco-Friendly Mode (on vEdge Cloud routers only)	Click On to configure a vEdge Cloud router not to use its CPU minimally or not at all when the router is not processing any packets.

To save the feature template, click Save.

*CLI equivalent:*

```

system
  admin-tech-on-failure
  allow-same-site-tunnels (on vEdge routers only)
  control-session-pps rate
  eco-friendly-mode (on vEdge Cloud routers only)
  host-policer-pps rate (on vEdge routers only)
  icmp-error-pps rate (on vEdge routers only)
  idle-timeout seconds
  multicast-buffer-percent percentage (on vEdge routers only)
  port-hop
  port-offset number
  route-consistency-check (on vEdge routers only)
  system-tunnel-mtu bytes
  timer
    dns-cache-timeout minutes
  track-default-gateway
  track-interface-tag number (on vEdge routers only)
  track-transport
  upgrade-confirm minutes
  [no] usb-controller (vEdge 1000 and 2000 routers only)
  vbond (dns-name | ip-address) local (on vEdge routers acting as vBond controllers)

```

## Release Information

Introduced in vManage NMS in Release 15.2.

In Releases 15.3.8 and 15.4.3, add Track Interface field.

In Release 17.1.0, add Route Consistency Check and Collect Admin Tech on Reboot fields.

In Release 17.2.0, add support for CLI idle timeout and ecofriendly mode.

In Release 17.2.2, add support for interface status tracking.

## T1/E1 Controller

Use the T1/E1 Controller template for Cisco IOS XE routers running the SD-WAN software.

---


## Configuration

To configure the T1/E1 interfaces in a VPN using vManage templates:

1. Create a T1/E1 Controller template to configure the T1 or E1 network interface module (NIM) parameters, as described in this article.
2. Create a VPN Interface T1/E1 feature template to configure T1/E1 interface parameters. See the VPN Interface T1/E1 help topic.
3. Create a VPN feature template to configure VPN parameters. See the [VPN](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. To create a template for VPN 0 or VPN 512:
  - a. Click the Transport & Management VPN tab located directly beneath the Description field, or scroll to the Transport & Management VPN section.
  - b. Under Additional VPN 0 Templates, located to the right of the screen, click VPN Interface.
  - c. From the VPN Interface drop-down, click Create Template. The VPN Interface T1/E1 template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN Interface Ethernet parameters.
6. To create a template for VPNs 1 through 511, and 513 through 65530:
  - a. Click the Service VPN tab located directly beneath the Description field, or scroll to the Service VPN section.
  - b. Click the Service VPN drop-down.
  - c. Under Additional VPN templates, located to the right of the screen, click VPN Interface.
  - d. From the VPN Interface drop-down, click Create Template. The VPN Interface Ethernet template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN Interface Ethernet parameters.



7. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
8. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure a T1 Controller

To configure a T1 controller, click the T1 radio button and configure the following parameters. Parameters marked with an asterisk are required to configure an interface.

Parameter Name	Description
Slot*	Enter the number of the slot in which the T1 NIM is installed.  <i>Range: 0 through 6</i>
Framing*	Enter the T1 frame type: <ul style="list-style-type: none"> <li><b>esf</b> —Send T1 frames as extended superframes. This is the default.</li> <li><b>sf</b> —Send T1 frames as superframes. Superframing is sometimes called D4 framing.</li> </ul>
Line Code	Select the line encoding to use to send T1 frames: <ul style="list-style-type: none"> <li><b>ami</b>—Use alternate mark inversion (AMI) as the linecode. AMI signaling uses frames grouped into superframes.</li> <li><b>b8zs</b>—Use bipolar 8-zero substitution as the linecode. This is the default. B8ZS uses frames that are grouping into extended superframes</li> </ul>
Clock Source	Select the clock source: <ul style="list-style-type: none"> <li><b>internal</b>—Use the controller framer as the reference clock.</li> <li><b>line</b>—Use phase-locked loop (PLL) on the interface. This is the default. When both T1 ports use line clocking and neither port is configured as the primary, by default, port 0 is the primary clock source and port 1 is the secondary clock source.</li> </ul>
Line Mode	If you choose the Line clock source, select whether the line is a primary or a secondary line.
Description	Enter a description for the controller.
Channel Group	Enter the number of the channel group. If you do so, you must enter a time slot in the Time Slot field. <i>Range: 0 through 30</i>
Time Slot	Enter the time slot or time slots that are part of the channel group. <i>Range: 1 through 24</i>
Cable Length	Select the cable length to configure the attenuation <ul style="list-style-type: none"> <li><b>long</b>—Attenuate the pulse from the transmitter using pulse equalization and line buildout. You can configure a long cable length for cables longer than 660 feet.</li> <li><b>short</b>—Set the transmission attenuation for cables that are 660 feet or shorter.</li> </ul> <p>There is no default length.</p>

Length	<p>If you specify a value in the Cable Length Field, enter the length of the cable.</p> <p>For short cables, the length values can be:</p> <ul style="list-style-type: none"> <li>• 110—Length from 0 through 110 feet</li> <li>• 220—Length from 111 through 220 feet</li> <li>• 330—Length from 221 through 330 feet</li> <li>• 440—Length from 331 through 440 feet</li> <li>• 550—Length from 441 through 550 feet</li> <li>• 660—Length from 551 through 660 feet</li> </ul> <p>For long cables, the length values can be:</p> <ul style="list-style-type: none"> <li>• 0 dB</li> <li>• -7.5 dB</li> <li>• -15 dB</li> <li>• -22.5 dB</li> </ul>
--------	---

To save the feature template, click Save.

## Configure an E1 Controller

To configure an E1 controller, click the E1 radio button and configure the following parameters. Parameters marked with an asterisk are required to configure an interface.

Parameter Name	Description
Slot*	<p>Enter the number of the slot in which the E1 NIM is installed.</p> <p><i>Range:</i> 0 through 6</p>
Framing*	<p>Enter the E1 frame type:</p> <ul style="list-style-type: none"> <li>• <b>crc4</b> —Use cyclic redundancy check 4 (CRC4). This is the default.</li> <li>• <b>no-crc4</b> —Do not use CRC4.</li> </ul>
Line Code*	<p>Select the line encoding to use to send E1 frames:</p> <ul style="list-style-type: none"> <li>• <b>ami</b>—Use alternate mark inversion (AMI) as the linecode.</li> <li>• <b>hdb3</b>—Use high-density bipolar 3 as the linecode. This is the default.</li> </ul>
Clock Source	<p>Select the clock source:</p> <ul style="list-style-type: none"> <li>• <b>internal</b>—Use the controller framer as the reference clock.</li> <li>• <b>line</b>—Use phase-locked loop (PLL) on the interface. This is the default.</li> </ul>
Line Mode	<p>If you choose the Line clock source, select whether the line is a primary or secondary line. If you configure both a primary and a secondary line, if the primary line fails, the PLL automatically switches to the secondary line. When the PLL on the primary line becomes active again, the PLL automatically switches back to the primary line.</p>

Description	Enter a description for the controller.
Channel Group	To configure the serial WAN on the E1 interface, enter a channel group number. <i>Range:</i> 0 through 30
Time Slot	For a channel group, configure the timeslot. <i>Range:</i> 1 through 31

To save the feature template, click Save.

## Release Information

Introduced in vManage NMS Release 18.1.1.

## VPN

Use the VPN template for all Viptela devices.

To configure VPNs for network segmentation using vManage templates:


1. Create VPN feature templates to configure VPN parameters, as described in this article. You create a separate VPN feature template for each VPN. For example, create one feature template for VPN 0, a second for VPN 1, and a third for VPN 512. For vManage NMSs and vSmart controllers, you can configure only VPNs 0 and 512. Create templates for these VPNs only if you want to modify the default settings for the VPN. For vEdge routers, you can create templates for these two VPNs and for additional VPN feature templates to segment service-side user networks.
  - VPN 0—Transport VPN, which carries control traffic via the configured WAN transport interfaces. Initially, VPN 0 contains all of a device's interfaces except for the management interface, and all interfaces are disabled.
  - VPN 512—Management VPN, which carries out-of-band network management traffic among the Viptela devices in the overlay network. The interface used for management traffic resides in VPN 512. By default, VPN 512 is configured and enabled on all vEdge routers except for vEdge 100. For controller devices, by default, VPN 512 is not configured.
  - VPNs 1 through 511, and 513 through 65530—VPNs on vEdge routers for service-side data traffic.
2. Create interface feature templates to configure the interfaces in the VPN. See the [VPN-Interface-Ethernet](#) help topic.
3. For vEdge routers, create interface feature templates to configure additional interfaces in the VPN. See the [VPN-Interface-GRE](#) , [VPN-Interface-PPP](#) , and [VPN-Interface-PPP-Ethernet](#) help topics.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. To create a template for VPN 0 or VPN 512:
  - a. Click the Transport & Management VPN tab located directly beneath the Description field, or scroll to the Transport & Management VPN section.
  - b. From the VPN 0 or VPN 512 drop-down, click Create Template. The VPN template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN parameters.
6. To create a template for VPNs 1 through 511, and 513 through 65530:

Configuration

- a. Click the Service VPN tab located directly beneath the Description field, or scroll to the Service VPN section.
- b. Click the Service VPN drop-down.
- c. From the VPN drop-down, click Create Template. The VPN template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN parameters.



7. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
8. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
-----------------	-------------------



Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure Basic VPN Parameters

To configure basic VPN parameters, select the Basic Configuration tab and then configure the following parameters. Parameters marked with an asterisk are required to configure a VPN.

Parameter Name	Description
VPN*	<p>Enter the numeric identifier of the VPN.</p> <p><i>Range for vEdge routers: 0 through 65530</i>  <i>Values for vSmart and vManage devices: 0, 512</i></p>
Name	Enter a name for the VPN.
Enhance ECMP keying on vEdge routers only)	Click On to enable the use in the ECMP hash key of Layer 4 source and destination ports, in addition to the combination of the source IP address, destination IP address, protocol, and DSCP field, as the ECMP hash key. ECMP keying is Off by default.
Enable TCP Optimization ( on vEdge routers only)	Click On to enable TCP optimization for a service-side VPN (a VPN other than VPN 0 and VPN 512). TCP optimization fine-tunes TCP to decrease round-trip latency and improve throughput for TCP traffic.
Save	Click Save to save the feature template.

To complete the configuration of the transport VPN on a vEdge router, you must configure at least one interface in VPN 0.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  ecmp-hash-key layer4 (on vEdge routers only)
  name text
  tcp-optimization (on vEdge routers only)
```

## Configure DNS and Static Hostname Mapping

To configure DNS addresses and static hostname mapping, select the DNS tab and configure the following parameters:

Parameter Name	Description
Primary DNS Address	Enter the IP address of the primary DNS server in this VPN.

## Configuration

Secondary DNS Address	Enter the IP address of a secondary DNS server in this VPN. This field appears only if you have specified a primary DNS address.
Hostname	Click Add New DNS, and enter the hostname of the DNS server. The name can be up to 128 characters.
List of IP Addresses	Enter up to eight IP addresses to associate with the hostname. Separate the entries with commas.

To save the DNS server configuration, click Add.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  dns ip-address (primary | secondary)
  host hostname ip ip-address
```

## Configure Route Advertisements to OMP

To configure, for this VPN, route advertisements to OMP, select the Advertise OMP tab and configure the parameters listed below. Route advertisements that you configure here apply to the specific VPN. If you configure route advertisements to OMP for both the VPN and the entire vEdge router (using the [OMP feature template](#)), both configurations are applied.

Parameter Name	Description
BGP	Click On to advertise BGP routes from this VPN to OMP.
Static	Click On to advertise static routes from this VPN to OMP.
Connected	Click On to advertise connected routes from this VPN to OMP.
OSPF	Click On to advertise OSPF routes from this VPN to OMP. By default OSPF interarea and intra-areas routes are advertised OMP. Click On again to advertise external OSPF routes.
Network	Click the Network tab and click On to advertise a specific prefix to OMP. Click Add New Prefix, enter the prefix, and click Add
Aggregate	Click the Aggregate tab and click On to aggregate a prefix before advertising it to OMP. Click Add New Aggregate, enter the prefix, click On again to advertise only the aggregated prefix, and click Add.

To save the route advertisement configuration, click Add.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  omp
    advertise (aggregate prefix [aggregate-only] | bgp | connected | network prefix | ospf type | static)
```

## Configure IPv4 Static Routes

To configure IPv4 static routes in a VPN, select the IPv4 Route tab. Then click Add New IPv4 Route, and configure the following parameters:

Parameter Name	Description
----------------	-------------

## Configuration

Prefix	Enter the IPv4 address or prefix, in decimal four-point-dotted notation, and the prefix length of the IPv4 static route to configure in the VPN.
Gateway	To configure the next hop to reach the static route, select one of the following: <ul style="list-style-type: none"> <li>Next Hop—Specify the IPv4 address of the next-hop router to use to reach the static route.</li> <li>Null0—Specify that the next hop is the null interface.</li> <li>VPN0—Direct packets to the transport VPN.</li> </ul> Then click the plus sign (+) below the Gateway field to configure information about the next hop.
Address	If you select Next Hop as the gateway, click Add Next Hop. Then enter the IP address of the next-hop router and an administrative distance for the route. The distance can be a value from 1 through 255. The default is 1. Then click Save.
Enable Null0	If you select Null0 as the gateway, in Enable Null0, click On to set the next hop to be the null interface. All packets sent to this interface are dropped without sending any ICMP messages. You can also set an administrative distance for the route. The distance can be a value from 1 through 255. The default is 1.
Enable VPN	If you select VPN as the gateway, in Enable VPN, click On to direct packets to the transport VPN. If NAT is enabled on the WAN interface, the packets can be forwarded to an Internet destination or other destination outside of the overlay network, effectively converting the vEdge router into a local Internet exit point. You must also enable NAT on a transport interface in VPN 0.

To save the configured IPv4 static routes, click Add.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
 ip route ip-address/subnet next-hop-address [administrative-distance]
```

## Configure IPv6 Static Routes

To configure IPv6 static routes in VPN 0, select the IPv6 Route tab. Then click Add New IPv6 Route, and configure the following parameters:

Parameter Name	Description
Prefix	Enter the IPv6 address or prefix, and the prefix length of the IPv6 static route to configure in VPN 0.
Gateway	To configure the next hop to reach the static route, select one of the following: <ul style="list-style-type: none"> <li>Next Hop—Specify the IPv6 address of the next-hop router to use to reach the static route.</li> <li>Null0—Specify that the next hop is the null interface.</li> <li>VPN—Direct packets to the transport VPN.</li> </ul>
Address	If you select Next Hop as the gateway, click Add Next Hop. Then enter the IP address of the next-hop router and an administrative distance for the route. The distance can be a value from 1 through 255. The default is 1.  To save the address, click Save
Enable Null0	If you select Null0 as the gateway, in Enable Null0, click On to set the next hop to be the null interface. All packets sent to this interface are dropped without sending any ICMP messages. You can also set an administrative distance for the route. The distance can be a value from 1 through 255. The default is 1.

Enable VPN	If you select VPN as the gateway, in Enable VPN, click On to direct packets to the transport VPN. If NAT is enabled on the WAN interface, the packets can be forwarded to an Internet destination or other destination outside of the overlay network, effectively converting the vEdge router into a local Internet exit point. You must also enable NAT on a transport interface in VPN 0.
------------	--

To save the configured IPv6 static routes, click Add.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn 0
  ipv6 route ip-address/subnet next-hop-address [administrative-distance]
```

## Configure Services

For a server VPN on a vEdge router (any VPN except VPN 0 and VPN 512), you can configure services that are either present on the router's local network or available on a device at a remote site that is reachable through a GRE tunnel.

To configure a service in a VPN, select the Service tab. Then click Add New Service, and configure the following parameters:

Parameter Name	Description
Service Type	Select the service available in the local VPN. <i>Values:</i> FW, IDP, IDS, netsvc1, netsvc2, netsvc3, netsvc4, TE
IP Address or Interface	Enter the location of the service: <ul style="list-style-type: none"> <li>If you select IP address, specify up to four IP address, separated by commas. The service is advertised to the vSmart controller only if one of the addresses can be resolved locally, at the local site, not via routes learned through OMP. You can configure up to four IP addresses.</li> <li>If you select Interface, specify one or two GRE interfaces. If you configure two, the first interface is the primary GRE tunnel, and the second is the backup tunnel.</li> </ul>

To save the service configuration, click Add.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  service service-name address ip-address
```

## Configure GRE-Specific Static Routes

To configure GRE-specific static routes in a service VPN (any VPN except VPN 0 and VPN 512 on a vEdge router), select the GRE Route tab. Then click Add New GRE Route, and configure the following parameters:

Parameter Name	Description
Prefix	Enter the IP address or prefix , in decimal four-part-dotted notation, and prefix length of the GRE-specific static route.
VPN ID	Enter the number of the VPN to reach the service. This must be VPN 0.
GRE Interface	Enter the name of one or two GRE tunnels to use to reach the service.

## Configuration

To save a GRE-specific static route, click Add.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
 ip gre-route prefix/length vpn 0 interface grenumber [gnumber2]
```

## Configure IPsec-Specific Static Routes

To configure IPsec-specific static routes in a service VPN (any VPN except VPN 0 and VPN 512 on a vEdge router), select the IPsec Route tab. Then click Add New IPsec Route, and configure the following parameters:

Parameter Name	Description
Prefix	Enter the IP address or prefix , in decimal four-part-dotted notation, and prefix length of the IPsec-specific static route.
VPN ID	Enter the number of the VPN to reach the IPsec tunnel. This must be VPN 0.
IPsec Interface	Enter the name of one or two IPsec tunnel interfaces. If you configure two interfaces, the first is the primary IPsec tunnel, and the second is the backup. All packets are sent only to the primary tunnel. If that tunnel fails, all packets are then sent to the secondary tunnel. If the primary tunnel comes back up, all traffic is moved back to the primary IPsec tunnel.

To save an IPsec-specific static route, click Add.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
 ip ipsec-route prefix/length vpn 0 interface ipsecnumber [ipsecnumber2]
```

## Release Information

Introduced in vManage NMS in Release 15.2.

In Release 15.4.3, add support for GRE tunnels.

In Release 16.3, add support for IPv6 in VPN 0.

In Release 17.2.0, add support for TE service.

In Release 18.2.0 add support for static routes to IPsec tunnels.

## VPN Interface Bridge

Use the VPN Interface Bridge template for all vEdge Cloud and vEdge router devices.


Integrated routing and bridging (IRB) allows vEdge routers in different bridge domains to communicate with each other. To enable IRB, create logical IRB interfaces to connect a bridge domain to a VPN. The VPN provides the Layer 3 routing services necessary so that traffic can be exchanged between different VLANs. Each bridge domain can have a single IRB interface and can connect to a single VPN, and a single VPN can connect to multiple bridge domains on a vEdge router.

To configure a bridge interface using vManage templates:

1. Create a VPN Interface Bridge feature template to configure parameters for logical IRB interfaces, as described in this article.
2. Create a Bridge feature template for each bridging domain, to configure the bridging domain parameters. See the [Bridge](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Service VPN tab located directly beneath the Description field, or scroll to the Service VPN section.
6. Click the Service VPN drop-down.



7. Under Additional VPN Templates, located to the right of the screen, click VPN Interface Bridge.
8. From the VPN Interface Bridge drop-down, click Create Template. The VPN Interface Bridge template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN Interface Bridge parameters.
9. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
10. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
-----------------	-------------------

Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Create a Bridging Interface

To configure an interface to use for bridging servers, select the Basic Configuration tab and click configure the following parameters. Parameters marked with an asterisk are required to configure bridging.

Parameter Name	Description
Shutdown*	Click No to enable the interface.
Interface name*	Enter the name of the interface, in the format <b>irb number</b> . The IRB interface number can be from 1 through 63, and must be the same as the VPN identifier configured in the Bridge feature template for the bridging domain that the IRB is connected to.
Description	Enter a description for the interface.
IPv4 Address*	Enter the IPv4 address of the router.
DHCP Helper	Enter up to eight IP addresses for DHCP servers in the network, separated by commas, to have the interface be a DHCP helper. A DHCP helper interface forwards BOOTP (Broadcast) DHCP requests that it receives from the specified DHCP servers.
Block Non-Source IP	Click Yes to have the interface forward traffic only if the source IP address of the traffic matches the interface's IP prefix range.
Secondary IP Address (on vEdge routers)	Click Add to configure up to four secondary IPv4 addresses for a service-side interface.

To save the template, click Save.

*CLI equivalent:*

```
vpn vpn-id
interface irbnumber
  description "text description"
  dhcp-helper ip-addresses
  ip address prefix/length
  mac-address mac-address
  mtu bytes
  secondary-address ipv4-address
  [no] shutdown
  tcp-mss-adjust bytes
```

## Apply Access Lists

To apply access lists to IRB interfaces, select the ACL tab and configure the following parameters:

Parameter Name	Description
Ingress ACL – IPv4	Click On, and specify the name of an IPv4 access list to packets being received on the interface.
Egress ACL– IPv4	Click On, and specify the name of an IPv4 access list to packets being transmitted on the interface.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  interface irbnumber
    access-list acl-name (in | out)
```

## Configure VRRP

To have an interface run the Virtual Router Redundancy Protocol (VRRP), which allows multiple routers to share a common virtual IP address for default gateway redundancy, select the VRRP tab. Then click Add New VRRP and configure the following parameters:

Parameter Name	Description
Group ID	Enter the virtual router ID, which is a numeric identifier of the virtual router. You can configure a maximum of 24 groups. <i>Range:</i> 1 through 255
Priority	Enter the priority level of the router. The router with the highest priority is elected as primary. If two vEdge routers have the same priority, the one with the higher IP address is elected as primary. <i>Range:</i> 1 through 254 <i>Default:</i> 100
Timer	Specify how often the VRRP primary sends VRRP advertisement messages. If secondary routers miss three consecutive VRRP advertisements, they elect a new primary. <i>Range:</i> 1 through 3600 seconds <i>Default:</i> 1 second
Track OMP Track Prefix List	By default, VRRP uses the state of the service (LAN) interface on which it is running to determine which vEdge router is the primary virtual router. If a vEdge router loses all its WAN control connections, the LAN interface still indicates that it is up even though the router is functionally unable to participate in VRRP. To take WAN side connectivity into account for VRRP, configure one of the following:  Track OMP—Click On for VRRP to track the Overlay Management Protocol (OMP) session running on the WAN connection. If the primary VRRP router loses all its OMP sessions, VRRP elects a new default gateway from those that have at least one active OMP session.  Track Prefix List—Track both the OMP session and a list of remote prefixes, which is defined in a prefix list configured on the local router. If the primary VRRP router loses all its OMP sessions, VRRP failover occurs as described for the Track OMP option. In addition, if reachability to one of the prefixes in the list is lost, VRRP failover occurs immediately, without waiting for the OMP hold timer to expire, thus minimizing the amount of overlay traffic is dropped while the vEdge routers determine the VRRP primary.
IP Address	Enter the IP address of the virtual router. This address must be different from the configured interface IP addresses of both the local vEdge router and the peer running VRRP.

To save the VRRP configuration, click Add.

To save the feature template, click Save.



## Configuration

*CLI equivalent:*

```

vpn vpn-id
  interface irbnumber[.subinterface]
    vrrp group-number
      ipv4 ip-address
      priority number
      timer seconds
      (track-omp | track-prefix-list list-name)

```

## Add ARP Table Entries

To configure static Address Resolution Protocol (ARP) table entries on the interface, select the ARP tab. Then click Add New ARP and configure the following parameters:

Parameter Name	Description
IP Address	Enter the IP address for the ARP entry in dotted decimal notation or as a fully qualified host name.
MAC Address	Enter the MAC address in colon-separated hexadecimal notation.

To save the ARP configuration, click Add.

To save the feature template, click Save.

*CLI equivalent:*

```

vpn vpn-id
  interface irbnumber
    arp
      ip address ip-address mac mac-address

```

## Configure Other Interface Properties

To configure other interface properties, select the Advanced tab and configure the following parameters:

Parameter Name	Description
MAC Address	Specify a MAC address to associate with the interface, in colon-separated hexadecimal notation.
IP MTU	Specify the maximum MTU size of packets on the interface. <i>Range:</i> 576 through 1804 <i>Default:</i> 1500 bytes
TCP MSS	Specify the maximum segment size (MSS) of TCP SYN packets passing through the vEdge router. By default, the MSS is dynamically adjusted based on the interface or tunnel MTU such that TCP SYN packets are never fragmented. <i>Range:</i> 552 to 1460 bytes <i>Default:</i> None
Clear-Don't-Fragment	Click On to clear the Don't Fragment (DF) bit in the IPv4 packet header for packets being transmitted out the interface. When the DF bit is cleared, packets larger than that interface's MTU are fragmented before being sent.
ARP Timeout	Specify how long it takes for a dynamically learned ARP entry to time out. <i>Range:</i> 0 through 2678400 seconds (744 hours) <i>Default:</i> 1200 seconds (20 minutes)
ICMP Redirect	Click Disable to disable ICMP redirect messages on the interface. By default, an interface allows ICMP redirect messages.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  interface irbnumber
    arp-timeout seconds
    clear-dont-fragment
    icmp-redirect-disable
    mac-address mac-address
    mtu bytes
    tcp-mss-adjust bytes
```

## Release Information

Introduced in vManage NMS in Release 15.3.

In Release 18.2, add support for disabling ICMP redirect messages.

## VPN Interface Cellular

Use the VPN Interface Cellular feature template to configure cellular module parameters on vEdge routers and Cisco IOS XE routers running the SD-WAN software.

To configure cellular interfaces using vManage templates:


1. Create a VPN Interface Cellular feature template to configure cellular module parameters, as described in this article.
2. Create a Cellular Profile template to configure the profiles used by the cellular modem. See the [Cellular Profile](#) help topic.
3. Create a VPN feature template to configure VPN parameters. See the [VPN](#) help topic.

## Navigate to the Template Screen

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Transport & Management VPN tab located directly beneath the Description field, or scroll to the Transport & Management VPN section.

Configuration

- Under Additional VPN 0 Templates, located to the right of the screen, click VPN Interface Cellular.



- From the VPN Interface Cellular drop-down, click Create Template. The VPN Interface Cellular template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN Interface Cellular parameters.
- In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
- In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <a href="#">attach a Viptela device to a device template</a> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>

Global (indicated by a globe icon)	Enter a value for the parameter, and apply that value to all devices.  Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.
------------------------------------	--

## Configure Basic Cellular Interface Functionality

To configure basic cellular interface functionality, select the Basic Configuration tab and configure the following parameters. Parameters marked with an asterisk are required to configure an interface. You must also configure a tunnel interface for the cellular interface.

Parameter Name	Description
Shutdown*	Click No to enable the interface.
Technology	Cellular technology. The default is <b>lte</b> . Other values are <b>auto</b> and <b>cdma</b> . For ZTP to work, the technology must be <b>auto</b> .
Interface Name*	Enter the name of the interface. It must be <b>cellular0</b> .
Profile ID*	Enter the identification number of the cellular profile. This is the profile identifier that you configure in the Cellular-Profile template. <i>Range: 1 through 15</i>
Description	Enter a description of the cellular interface.
IPv4 Configuration	To configure a static address, click Static and enter an IPv4 address.  To set the interface as a DHCP client so that the interface to receive its IP address from a DHCP server, click Dynamic. You can optionally set the DHCP distance to specify the administrative distance of routes learned from a DHCP server. The default DHCP distance is 1.
IPv6 Configuration	To configure a static address for an interface in VPN 0, click Static and enter an IPv6 address.  To set the interface as a DHCP client so that the interface to receive its IP address from a DHCP server, click Dynamic. You can optionally set the DHCP distance to specify the administrative distance of routes learned from a DHCP server. The default DHCP distance is 1. You can optionally enable DHCP rapid commit, to speed up the assignment of IP addresses.
DHCP Helper	Enter up to four IP addresses for DHCP servers in the network, separated by commas, to have the interface be a DHCP helper. A DHCP helper interface forwards BOOTP (Broadcast) DHCP requests that it receives from the specified DHCP servers.
Block Non-Source IP	Click Yes to have the interface forward traffic only if the source IP address of the traffic matches the interface's IP prefix range.
Bandwidth Upstream	For transmitted traffic, set the bandwidth above which to generate notifications. <i>Range: 1 through <math>(2^{32} / 2) - 1</math> kbps</i>
Bandwidth Downstream	For received traffic, set the bandwidth above which to generate notifications. <i>Range: 1 through <math>(2^{32} / 2) - 1</math> kbps</i>
IP MTU*	Enter 1428 to set the MTU size, in bytes. This value must be 1428. You cannot use a different value.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn 0
  interface cellular0
    bandwidth-downstream kbps
    bandwidth-upstream kbps
```

## Configuration

```

block-non-source-ip
(ip address ip-address/length | ip dhcp-client [dhcp-distance number])
(ipv6 address ipv6-prefix/length | ipv6 dhcp-client [dhcp-distance number] [dhcp-rapid-comit])
mtu 1428
profile number
no shutdown

```

## Create a Tunnel Interface

To configure an interface in VPN 0 to be a WAN transport connection, you must configure a tunnel interface on the cellular interface. The tunnel, which provides security from attacks, is used to send the phone number. At a minimum, select On and select a color for the interface, as described in the previous section. You can generally accept the system defaults for the remainder of the tunnel interface settings.

To configure a tunnel interface, select the Tunnel tab and configure the following parameters. Parameters marked with an asterisk are required to configure a cellular interface.

Parameter Name	Description
Tunnel Interface*	Click On to create a tunnel interface.
Color*	Select a color for the TLOC. The color typically used for cellular interface tunnels is <b>lte</b> .
Control Connection	The default is On, which establishes a control connection for the TLOC. If the router has multiple TLOCs, click No to have a tunnel not establish a TLOC.
Maximum Control Connections	Set the maximum number of vSmart controllers that the WAN tunnel interface can connect to. To have the tunnel establish no control connections, set the number to 0. <i>Range:</i> 0 through 8  <i>Default:</i> 2
vBond As STUN Server	Click On to enable Session Traversal Utilities for NAT (STUN) to allow the tunnel interface to discover its public IP address and port number when the router is located behind a NAT.
Exclude Control Group List	Set the identifiers of one or more vSmart controller groups that this tunnel is not allowed to establish control connections with. <i>Range:</i> 0 through 100
vManage Connection Preference	Set the preference for using the tunnel to exchange control traffic with the vManage NMS. <i>Range:</i> 0 through 9 <i>Default:</i> 5
Low-Bandwidth Link	Click On to set the tunnel interface as a low-bandwidth link.
Allow Service	Click On or Off for each service to allow or disallow the service on the cellular interface.

To configure additional tunnel interface parameters, click Advanced Options and configure the following parameters:

Parameter Name	Description
GRE	Use GRE encapsulation on the tunnel interface. By default, GRE is disabled.  If you select both IPsec and GRE encapsulations, two TLOCs are created for the tunnel interface that have the same IP addresses and colors, but that differ by their encapsulation.
IPsec	Use IPsec encapsulation on the tunnel interface. By default, IPsec is enabled.  If you select both IPsec and GRE encapsulations, two TLOCs are created for the tunnel interface that have the same IP addresses and colors, but that differ by their encapsulation.

## Configuration

IPsec Preference	Enter a value to set the preference for directing traffic to the tunnel. A higher value is preferred over a lower value. <i>Range:</i> 0 through 4294967295 <i>Default:</i> 0
IPsec Weight	Enter a weight to use to balance traffic across multiple TLOCs. A higher value sends more traffic to the tunnel. <i>Range:</i> 1 through 255 <i>Default:</i> 1
Carrier	Select the carrier name or private network identifier to associate with the tunnel. <i>Values:</i> carrier1, carrier2, carrier3, carrier4, carrier5, carrier6, carrier7, carrier8, default <i>Default:</i> default
Bind Loopback Tunnel	Enter the name of a physical interface to bind to a loopback interface. The interface name has the format <b>ge slot / port</b> .
Last-Resort Circuit	Use the tunnel interface as the circuit of last resort
NAT Refresh Interval	Set the interval between NAT refresh packets sent on a DTLS or TLS WAN transport connection. <i>Range:</i> 1 through 60 seconds <i>Default:</i> 5 seconds
Hello Interval	Enter the interval between Hello packets sent on a DTLS or TLS WAN transport connection. <i>Range:</i> 100 through 10000 milliseconds <i>Default:</i> 1000 milliseconds (1 second)
Hello Tolerance	Enter the time to wait for a Hello packet on a DTLS or TLS WAN transport connection before declaring that transport tunnel to be down.  <i>Range:</i> 12 through 60 seconds <i>Default:</i> 12 seconds

To save the feature template, click Save.

*CLI equivalent:*

```

vpn 0
  interface cellular0
    tunnel-interface
      allow-service service-name
      bind interface-name
      carrier carrier-name
      color color
      encapsulation (gre | ipsec)
        preference number
        weight number
      exclude-controller-group-list number
      hello-interval milliseconds
      hello-tolerance seconds
      hold-time milliseconds
      low-bandwidth-link
      max-control-connections number
      last-resort-circuit
      nat-refresh-interval seconds
      vbond-as-stun-server
      vmanage-connection-preference number

```

## Configure the Cellular Interface as a NAT Device

To configure a cellular interface to act as a NAT device for applications such as port forwarding, select the NAT tab, click On and configure the following parameters:

Parameter Name	Description
NAT	Click On to have the interface act as a NAT device.
Refresh Mode	Select how NAT mappings are refreshed, either outbound or bidirectional (outbound and inbound). <i>Default</i> : Outbound
UDP Timeout	Specify when NAT translations over UDP sessions time out. <i>Range</i> : 1 through 65536 minutes <i>Default</i> : 1 minutes
TCP Timeout	Specify when NAT translations over TCP sessions time out. <i>Range</i> : 1 through 65536 minutes <i>Default</i> : 60 minutes (1 hour)
Block ICMP	Select On to block inbound ICMP error messages. By default, a router acting as a NAT device receives these error messages. <i>Default</i> : Off
Respond to Ping	Select On to have the router respond to ping requests to the NAT interface's IP address that are received from the public side of the connection.

To create a port forwarding rule, click Add New Port Forwarding Rule and configure the following parameters. You can define up to 128 port-forwarding rules to allow requests from an external network to reach devices on the internal network.

Parameter Name	Description
Port Start Range	Enter a port number to define the port or first port in the range of interest. <i>Range</i> : 0 through 65535
Port End Range	Enter the same port number to apply port forwarding to a single port, or enter a larger number to apply it to a range of ports. <i>Range</i> : 0 through 65535
Protocol	Select the protocol to which to apply the port-forwarding rule, either TCP or UDP. To match the same ports for both TCP and UDP traffic, configure two rules.
VPN	Specify the private VPN in which the internal server resides. This VPN is one of the VPN identifiers in the overlay network. <i>Range</i> : 0 through 65530
Private IP	Specify the IP address of the internal server to which to direct traffic that matches the port-forwarding rule.

To save a port forwarding rule, click Add.

To save the feature template, click Save.

### CLI equivalent:

```
vpn 0
 interface cellular0
   nat
     block-icmp-error
     port-forward port-start port-number1 port-end port-number2
       proto (tcp | udp) private-ip-address ip address private-vpn vpn-id
     refresh (bi-directional | outbound)
     respond-to-ping
     tcp-timeout minutes
     udp-timeout minutes
```

## Apply Access Lists

To configure a shaping rate to a cellular interface and to apply a QoS map, a rewrite rule, access lists, and policers to a router interface, select the ACL/QoS tab and configure the following parameters:

Parameter Name	Description
Shaping rate	Configure the aggregate traffic transmission rate on the interface to be less than line rate, in kilobits per second (kbps).
QoS map	Specify the name of the QoS map to apply to packets being transmitted out the interface.
Rewrite rule	Click On, and specify the name of the rewrite rule to apply on the interface.
Ingress ACL – IPv4	Click On, and specify the name of an IPv4 access list to packets being received on the interface.
Egress ACL – IPv4	Click On, and specify the name of an IPv4 access list to packets being transmitted on the interface.
Ingress ACL – IPv6	Click On, and specify the name of an IPv6 access list to packets being received on the interface.
Egress ACL – IPv6	Click On, and specify the name of an IPv6 access list to packets being transmitted on the interface.
Ingress policer	Click On, and specify the name of the policer to apply to packets being received on the interface.
Egress policer	Click On, and specify the name of the policer to apply to packets being transmitted on the interface.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn 0
  interface cellular0
    access-list acl-name (in | out)
    ipv6 access-list acl-name (in | out)
    policer policer-name (in |out)
    qos-map name
    rewrite-rule name
    shaping-rate name
```

## Add ARP Table Entries

To configure static Address Resolution Protocol (ARP) table entries on the interface, select the ARP tab. Then click Add New ARP and configure the following parameters:

Parameter Name	Description
IP Address	Enter the IP address for the ARP entry in dotted decimal notation or as a fully qualified host name.
MAC Address	Enter the MAC address in colon-separated hexadecimal notation.

To save the ARP configuration, click Add.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  interface irbnumber
```



## Configuration

```
arp
ip address ip-address mac mac-address
```

## Configure Other Interface Properties

To configure other interface properties, select the Advanced tab and configure the following parameters.

Parameter Name	Description
PMTU Discovery	Click On to enable path MTU discovery on the interface, to allow the router to determine the largest MTU size supported without requiring packet fragmentation.
TCP MSS	Specify the maximum segment size (MSS) of TCP SYN packets passing through the router. By default, the MSS is dynamically adjusted based on the interface or tunnel MTU such that TCP SYN packets are never fragmented. <i>Range:</i> 552 to 1460 bytes <i>Default:</i> None
Clear-Don't-Fragment	Click On to clear the Don't Fragment (DF) bit in the IPv4 packet header for packets being transmitted out the interface. When the DF bit is cleared, packets larger than that interface's MTU are fragmented before being sent.
Static Ingress QoS	Select a queue number to use for incoming traffic. <i>Range:</i> 0 through 7
ARP Timeout	Specify how long it takes for a dynamically learned ARP entry to time out. <i>Range:</i> 0 through 2678400 seconds (744 hours) <i>Default:</i> 1200 seconds (20 minutes)
Autonegotiate	Click Off to turn off autonegotiation. By default, an interface runs in autonegotiation mode.
TLOC Extension	Enter the name of a physical interface on the same router that connects to the WAN transport. This configuration then binds this service-side interface to the WAN transport. A second router at the same site that itself has no direct connection to the WAN (generally because the site has only a single WAN connection) and that connects to this service-side interface is then provided with a connection to the WAN.
Tracker	Enter the name of a tracker to track the status of transport interfaces that connect to the internet.
ICMP Redirect	Click Disable to disable ICMP redirect messages on the interface. By default, an interface allows ICMP redirect messages.

To save the feature template, click Save.

### CLI equivalent:

```
vpn 0
interface cellular0
  arp-timeout seconds
  [no] autonegotiate
  clear-dont-fragment
  icmp-redirect-disable
  mtu 1428
  pmtu
  static-ingress-qos number
  tcp-mss-adjust bytes
  tloc-extension interface-name
  tracker tracker-name
```

## Release Information

Introduced in vManage NMS in Release 16.1.

In Release 16.2, add circuit of last resort and its associated hold time.

In Release 16.3, add support for IPv6.

In Release 17.2.2, add support for tracker interface status.

In Release 18.2, add support for disabling ICMP redirect messages.

## VPN Interface DSL PPPoA

Use the VPN Interface DSL PPPoA template for Cisco IOS XE routers.


You configure PPP-over-ATM interfaces on routers with DSL NIM modules, to provide support for service provider digital subscriber line (DSL) functionality.

To configure DSL interfaces on Cisco routers using vManage templates:

1. Create a VPN Interface DSL PPPoA feature template to configure ATM interface parameters, as described in this article.
2. Create a VPN feature template to configure VPN parameters. See the [VPN](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Transport & Management VPN tab located directly beneath the Description field, or scroll to the Transport & Management VPN section.
6. Under Additional VPN 0 Templates, located to the right of the screen, click VPN Interface DSL PPPoA.
7. From the VPN Interface DSL PPPoA drop-down, click Create Template. The VPN Interface DSL PPPoA template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN Interface PPP parameters.



8. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
9. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <a href="#">attach a Viptela device to a device template</a> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>

Global (indicated by a globe icon)	Enter a value for the parameter, and apply that value to all devices.  Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.
------------------------------------	--

## Configure VDSL Controller Functionality

To configure basic VDSL controller functionality in a VPN, select the Basic Configuration tab and configure the following parameters. Required parameters are indicated with an asterisk.

Parameter Name	Description
Shutdown*	Click No to enable the VDSL controller interface.
Controller VDSL Slot*	Enter the slot number of the controller VDSL interface, in the format <i>slot / subslot / port</i> (for example, 0/2/0).
Mode*	Select the operating mode of the VDSL controller from the drop-down: <ul style="list-style-type: none"> <li>Auto—Default mode.</li> <li>ADSL1—Use ITU G.992.1 Annex A full-rate mode, which provides a downstream rate of 1.3 Mbps and an upstream rate of 1.8 Mbps.</li> <li>ADSL2—Use ITU G.992.3 Annex A, Annex L, and Annex M, which provides a downstream rate of 12 Mbps and an upstream rate of 1.3 Mbps.</li> <li>ADSL2+— Use ITU G.992.5 Annex A and Annex M, which provides a downstream rate of 24 Mbps and an upstream rate of 3.3 Mbps.</li> <li>ANSI—Operate in ADSL2/2+ mode, as defined in ITU G.991.1, G.992.3, and G992.5, Annex A and Annex M, and in VDSL2 mode, as defined in ITU-T G993.2.</li> <li>VDSL2—Operate in VDSL2 mode, as defined in ITU-T G.993.2, which uses frequencies of up to 30 MHz to provide a downstream rate of 200 Mbps and an upstream rate of 100 Mbps.</li> </ul>
VDSL Modem Configuration	Enter a command to send to the DSL modem in the NIM module. If the command is valid, it is executed and the results are returned to the vManage NMS. If the command is not valid, it is not executed.
SRA	Enabled by default. Click No to disable seamless rate adaptation on the interface. SRA adjusts the line rate based on current line conditions.

To save the feature template, click Save.

## Configure the ATM Interface

To configure an ATM interface on the VDSL controller, select the ATM tab and configure the following parameters. You must configure all parameters.

Parameter Name	Description
ATM Interface Name	Enter a name for the ATM interface, in the format <i>subslot / port</i> (for example 2/0). You do not need to enter the slot number, because it must always be 0.
Description	Enter a description for the interface.
VPI and VCI	Create an ATM permanent virtual circuit (PVC), in the format <i>vpi / vci</i> , Enter values for the virtual path identifier (VPI) and the virtual channel identifier (VCI).

## Configuration

Encapsulation	Select the ATM adaptation layer (AAL) and encapsulation type to use on the ATM PVC from the drop-down: <ul style="list-style-type: none"> <li>AAL5 MUX—Dedicate the PVC to a single protocol.</li> <li>AAL5 NLPID—Use NLPID multiplexing.</li> <li>AAL5 SNAP—Multiplex two or more protocols on the same PVC.</li> </ul>
Dialer Pool Member	Enter the number of the dialer pool to which the interface belongs. It can be a value from 1 through 255.
VBR-NRT	Configure variable bit rate non-real-time parameters: <ul style="list-style-type: none"> <li>Peak Cell Rate—Enter a value from 48 through 25000 Kbps.</li> <li>Sustainable Cell Rate—Enter the sustainable cell rate, in Kbps.</li> <li>Maximum Burst Size—This size can be 1 cell.</li> </ul>
VBR-RT	Configure variable bit rate real-time parameters: <ul style="list-style-type: none"> <li>Peak Cell Rate—Enter a value from 48 through 25000 Kbps.</li> <li>Average Cell Rate—Enter the average cell rate, in Kbps.</li> <li>Maximum Burst Size—This size can be 1 cell.</li> </ul>

To save the feature template, click Save.

## Configure the PPP Authentication Protocol

To configure the PPP authentication protocol, select the PPP tab and configure the following parameters:

Parameter Name	Description
Authentication Protocol	Select the authentication protocol used by the MLP: <ul style="list-style-type: none"> <li>CHAP—Enter the hostname and password provided by your Internet Service Provider (ISP). <i>hostname</i> can be up to 255 characters.</li> <li>PAP—Enter the username and password provided by your ISP. <i>username</i> can be up to 255 characters.</li> <li>PAP and CHAP—Configure both authentication protocols. Enter the login credentials for each protocol. To use the same username and password for both, click Same Credentials for PAP and CHAP.</li> </ul>

To save the feature template, click Save.

## Create a Tunnel Interface

On vEdge routers, you can configure up to four tunnel interfaces. This means that each vEdge router can have up to four TLOCs.

For the control plane to establish itself so that the overlay network can function, you must configure WAN transport interfaces in VPN 0.

To configure a tunnel interface for the multilink interface, select the Tunnel Interface tab and configure the following parameters:

Parameter Name	Description
Tunnel Interface	Click On to create a tunnel interface.
Color	Select a color for the TLOC.

Control Connection	If the vEdge router has multiple TLOCs, click No to have the tunnel not establish a TLOC. The default is On, which establishes a control connection for the TLOC.
Maximum Control Connections	Specify the maximum number of vSmart controllers that the WAN tunnel interface can connect to. To have the tunnel establish no control connections, set the number to 0.  <i>Range: 0 through 8</i> <i>Default: 2</i>
vBond As STUN Server	Click On to enable Session Traversal Utilities for NAT (STUN) to allow the tunnel interface to discover its public IP address and port number when the vEdge router is located behind a NAT.
Exclude Controller Group List	Set the vSmart controllers that the tunnel interface is not allowed to connect to. <i>Range: 0 through 100</i>
vManage Connection Preference	Set the preference for using a tunnel interface to exchange control traffic with the vManage NMS. <i>Range: 0 through 8</i> <i>Default: 5</i>
Port Hop	Click On to enable port hopping, or click Off to disable it. When a router is behind a NAT, port hopping rotates through a pool of preselected OMP port numbers (called base ports) to establish DTLS connections with other routers when a connection attempt is unsuccessful. The default base ports are 12346, 12366, 12386, 12406, and 12426. To modify the base ports, set a port offset value. <i>Default: Enabled</i>
Low-Bandwidth Link	Select to characterize the tunnel interface as a low-bandwidth link.
Allow Service	Select On or Off for each service to allow or disallow the service on the interface.

To configure additional tunnel interface parameters, click Advanced Options and configure the following parameters:

Parameter Name	Description
GRE	Use GRE encapsulation on the tunnel interface. By default, GRE is disabled.  If you select both IPsec and GRE encapsulations, two TLOCs are created for the tunnel interface that have the same IP addresses and colors, but that differ by their encapsulation.
IPsec	Use IPsec encapsulation on the tunnel interface. By default, IPsec is enabled.  If you select both IPsec and GRE encapsulations, two TLOCs are created for the tunnel interface that have the same IP addresses and colors, but that differ by their encapsulation.
IPsec Preference	Specify a preference value for directing traffic to the tunnel. A higher value is preferred over a lower value.  <i>Range: 0 through 4294967295</i> <i>Default: 0</i>
IPsec Weight	Enter a weight to use to balance traffic across multiple TLOCs. A higher value sends more traffic to the tunnel.  <i>Range: 1 through 255</i> <i>Default: 1</i>
Carrier	Select the carrier name or private network identifier to associate with the tunnel.  <i>Values: carrier1, carrier2, carrier3, carrier4, carrier5, carrier6, carrier7, carrier8, default</i> <i>Default: default</i>

## Configuration

Bind Loopback Tunnel	Enter the name of a physical interface to bind to a loopback interface.
Last-Resort Circuit	Select to use the tunnel interface as the circuit of last resort.
NAT Refresh Interval	Enter the interval between NAT refresh packets sent on a DTLS or TLS WAN transport connection. <i>Range:</i> 1 through 60 seconds <i>Default:</i> 5 seconds
Hello Interval	Enter the interval between Hello packets sent on a DTLS or TLS WAN transport connection. <i>Range:</i> 100 through 10000 milliseconds <i>Default:</i> 1000 milliseconds (1 second)
Hello Tolerance	Enter the time to wait for a Hello packet on a DTLS or TLS WAN transport connection before declaring that transport tunnel to be down.  <i>Range:</i> 12 through 60 seconds <i>Default:</i> 12 seconds

## Apply Access Lists

To apply a rewrite rule, access lists, and policers to a router interface, select the ACL tab and configure the following parameters:

Parameter Name	Description
Shaping rate	Configure the aggregate traffic transmission rate on the interface to be less than line rate, in kilobits per second (kbps).
QoS map	Specify the name of the QoS map to apply to packets being transmitted out the interface.
Rewrite Rule	Click On, and specify the name of the rewrite rule to apply on the interface.
Ingress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being received on the interface.
Egress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being transmitted on the interface.
Ingress ACL – IPv6	Click On, and specify the name of the access list to apply to IPv6 packets being received on the interface.
Egress ACL – IPv6	Click On, and specify the name of the access list to apply to IPv6 packets being transmitted on the interface.
Ingress Policer	Click On, and specify the name of the policer to apply to packets being received on the interface.
Egress Policer	Click On, and specify the name of the policer to apply to packets being transmitted on the interface.

To save the feature template, click Save.

## Configure Other Interface Properties

To configure other interface properties, select the Advanced tab and configure the following properties:

Parameter Name	Description
PMTU Discovery	Click On to enable path MTU discovery on the interface, to allow the router to determine the largest MTU size supported without requiring packet fragmentation.

TCP MSS	Specify the maximum segment size (MSS) of TCP SYN packets passing through the vEdge router. By default, the MSS is dynamically adjusted based on the interface or tunnel MTU such that TCP SYN packets are never fragmented. <i>Range: 552 to 1460 bytes</i> <i>Default: None</i>
Clear Dont Fragment	Click On to clear the Don't Fragment bit in the IPv4 packet header for packets being transmitted out the interface. When the DF bit is cleared, packets larger than that interface's MTU are fragmented before being sent.
Static Ingress QoS	Select a queue number to use for incoming traffic. <i>Range: 0 through 7</i>
Autonegotiate	Click Off to turn off autonegotiation. By default, an interface runs in autonegotiation mode.
TLOC Extension	Enter the name of the physical interface on the same router that connects to the WAN transport circuit. This configuration then binds this service-side interface to the WAN transport. A second vEdge router at the same site that itself has no direct connection to the WAN (generally because the site has only a single WAN connection) and that connects to this service-side interface is then provided with a connection to the WAN.

To save the feature template, click Save.

## Release Information

Introduced in vManage NMS in Release 18.3.

## VPN Interface DSL PPPoE

Use the VPN Interface DSL PPPoE template for Cisco IOS XE routers.

You configure PPP-over-Ethernet interfaces on routers with DSL NIM modules, to provide support for service provider digital subscriber line (DSL) functionality.


To configure DSL interfaces on Cisco routers using vManage templates:

1. Create a VPN Interface DSL PPPoE feature template to configure PPP-over-Ethernet interface parameters, as described in this article.
2. Create a VPN feature template to configure VPN parameters. See the [VPN](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Transport & Management VPN tab located directly beneath the Description field, or scroll to the Transport & Management VPN section.
6. Under Additional VPN 0 Templates, located to the right of the screen, click VPN Interface DSL PPPoE.
7. From the VPN Interface DSL PPPoE drop-down, click Create Template. The VPN Interface DSL PPPoE template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining PPPoE interface parameters.





8. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
9. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <a href="#">attach a Viptela device to a device template</a> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure VDSL Controller Functionality

To configure basic VDSL controller functionality in a VPN, select the Basic Configuration tab and configure the following parameters. Required parameters are indicated with an asterisk.

Parameter Name	Description
Shutdown*	Click No to enable the VDSL controller interface.
Controller VDSL Slot*	Enter the slot number of the controller VDSL interface, in the format <i>slot / subslot / port</i> (for example, 0/2/0).
Mode*	Select the operating mode of the VDSL controller from the drop-down: <ul style="list-style-type: none"> <li>Auto—Default mode.</li> <li>ADSL1—Use ITU G.992.1 Annex A full-rate mode, which provides a downstream rate of 1.3 Mbps and an upstream rate of 1.8 Mbps.</li> <li>ADSL2—Use ITU G.992.3 Annex A, Annex L, and Annex M, which provides a downstream rate of 12 Mbps and an upstream rate of 1.3 Mbps.</li> <li>ADSL2+— Use ITU G.992.5 Annex A and Annex M, which provides a downstream rate of 24 Mbps and an upstream rate of 3.3 Mbps.</li> <li>ANSI—Operating in ADSL2/2+ mode, as defined in ITU G.991.1, G.992.3, and G992.5, Annex A and Annex M, and in VDSL2 mode, as defined in ITU-T G993.2.</li> <li>VDSL2—Operate in VDSL2 mode, as defined in ITU-T G.993.2, which uses frequencies of up to 30 MHz to provide a downstream rate of 200 Mbps and an upstream rate of 100 Mbps..</li> </ul>
VDSL Modem Configuration	Enter a command to send to the DSL modem in the NIM module. If the command is valid, it is executed and the results are returned to the vManage NMS. If the command is not valid, it is not executed.
SRA	Click Yes to enable seamless SRA adaptation on the interface. SRA adjusts the line rate based on current line conditions.

To save the feature template, click Save.

## Configure the Ethernet Interface

To configure an Ethernet interface on the VDSL controller, select the Ethernet tab and configure the following parameters. You must configure all parameters.

Parameter Name	Description
Ethernet Interface Name	Enter a name for the Ethernet interface, in the format <i>subslot / port</i> (for example 2/0). You do not need to enter the slot number, because it must always be 0.
VLAN ID	Enter the VLAN identifier of the Ethernet interface.
Description	Enter a description for the interface.
Dialer Pool Member	Enter the number of the dialer pool to which the interface belongs. It can be a value from 1 through 255.
PPP Max Payload	Enter the maximum receive unit (MRU) value to be negotiated during PPP Link Control Protocol (LCP) negotiation. <i>Range:</i> 64 through 1792 bytes
Dialer IP	Configure the IP prefix of the dialer interface. This prefix is that of the node in the destination that the interface calls. <ul style="list-style-type: none"> <li>Negotiated—Use the address that is obtained during IPCP negotiation.</li> </ul>

To save the feature template, click Save.

## Configure the PPP Authentication Protocol

To configure the PPP authentication protocol, select the PPP tab and configure the following parameters:

Parameter Name	Description
Authentication Protocol	<p>Select the authentication protocol used by the MLP:</p> <ul style="list-style-type: none"> <li>CHAP—Enter the hostname and password provided by your Internet Service Provider (ISP). <i>hostname</i> can be up to 255 characters.</li> <li>PAP—Enter the username and password provided by your ISP. <i>username</i> can be up to 255 characters.</li> <li>PAP and CHAP—Configure both authentication protocols. Enter the login credentials for each protocol. To use the same username and password for both, click Same Credentials for PAP and CHAP.</li> </ul>

To save the feature template, click Save.

## Create a Tunnel Interface

On IOS XE routers, you can configure up to four tunnel interfaces. This means that each router can have up to four TLOCs.

For the control plane to establish itself so that the overlay network can function, you must configure WAN transport interfaces in VPN 0.

To configure a tunnel interface for the multilink interface, select the Tunnel Interface tab and configure the following parameters:

Parameter Name	Description
Tunnel Interface	Click On to create a tunnel interface.
Color	Select a color for the TLOC.
Control Connection	If the router has multiple TLOCs, click No to have the tunnel not establish a TLOC. The default is On, which establishes a control connection for the TLOC.
Maximum Control Connections	<p>Specify the maximum number of vSmart controllers that the WAN tunnel interface can connect to. To have the tunnel establish no control connections, set the number to 0.</p> <p><i>Range:</i> 0 through 8 <i>Default:</i> 2</p>
vBond As STUN Server	Click On to enable Session Traversal Utilities for NAT (STUN) to allow the tunnel interface to discover its public IP address and port number when the router is located behind a NAT.
Exclude Controller Group List	<p>Set the vSmart controllers that the tunnel interface is not allowed to connect to.</p> <p><i>Range:</i> 0 through 100</p>
vManage Connection Preference	<p>Set the preference for using a tunnel interface to exchange control traffic with the vManage NMS.</p> <p><i>Range:</i> 0 through 8 <i>Default:</i> 5</p>
Port Hop	<p>Click On to enable port hopping, or click Off to disable it. When a router is behind a NAT, port hopping rotates through a pool of preselected OMP port numbers (called base ports) to establish DTLS connections with other routers when a connection attempt is unsuccessful. The default base ports are 12346, 12366, 12386, 12406, and 12426. To modify the base ports, set a port offset value.</p> <p><i>Default:</i> Enabled</p>

Low-Bandwidth Link	Select to characterize the tunnel interface as a low-bandwidth link.
Allow Service	Select On or Off for each service to allow or disallow the service on the interface.

To configure additional tunnel interface parameters, click Advanced Options and configure the following parameters:

Parameter Name	Description
GRE	Use GRE encapsulation on the tunnel interface. By default, GRE is disabled.  If you select both IPsec and GRE encapsulations, two TLOCs are created for the tunnel interface that have the same IP addresses and colors, but that differ by their encapsulation.
IPsec	Use IPsec encapsulation on the tunnel interface. By default, IPsec is enabled.  If you select both IPsec and GRE encapsulations, two TLOCs are created for the tunnel interface that have the same IP addresses and colors, but that differ by their encapsulation.
IPsec Preference	Specify a preference value for directing traffic to the tunnel. A higher value is preferred over a lower value.  <i>Range:</i> 0 through 4294967295 <i>Default:</i> 0
IPsec Weight	Enter a weight to use to balance traffic across multiple TLOCs. A higher value sends more traffic to the tunnel.  <i>Range:</i> 1 through 255 <i>Default:</i> 1
Carrier	Select the carrier name or private network identifier to associate with the tunnel.  <i>Values:</i> carrier1, carrier2, carrier3, carrier4, carrier5, carrier6, carrier7, carrier8, default <i>Default:</i> default
Bind Loopback Tunnel	Enter the name of a physical interface to bind to a loopback interface.
Last-Resort Circuit	Select to use the tunnel interface as the circuit of last resort.
NAT Refresh Interval	Enter the interval between NAT refresh packets sent on a DTLS or TLS WAN transport connection.  <i>Range:</i> 1 through 60 seconds <i>Default:</i> 5 seconds
Hello Interval	Enter the interval between Hello packets sent on a DTLS or TLS WAN transport connection.  <i>Range:</i> 100 through 10000 milliseconds <i>Default:</i> 1000 milliseconds (1 second)
Hello Tolerance	Enter the time to wait for a Hello packet on a DTLS or TLS WAN transport connection before declaring that transport tunnel to be down.  <i>Range:</i> 12 through 60 seconds <i>Default:</i> 12 seconds

## Configure the Interface as a NAT Device

To configure an interface to act as a NAT device for applications such as port forwarding, select the NAT tab, click On and configure the following parameters:

## Configuration

Parameter Name	Description
NAT	Click On to have the interface act as a NAT device.
Refresh Mode	Select how NAT mappings are refreshed, either outbound or bidirectional (outbound and inbound). <i>Default</i> : Outbound
UDP Timeout	Specify when NAT translations over UDP sessions time out. <i>Range</i> : 1 through 65536 minutes <i>Default</i> : 1 minutes
TCP Timeout	Specify when NAT translations over TCP sessions time out. <i>Range</i> : 1 through 65536 minutes <i>Default</i> : 60 minutes (1 hour)
Block ICMP	Select On to block inbound ICMP error messages. By default, a router acting as a NAT device receives these error messages. <i>Default</i> : Off
Respond to Ping	Select On to have the router respond to ping requests to the NAT interface's IP address that are received from the public side of the connection.

To create a port forwarding rule, click Add New Port Forwarding Rule and configure the following parameters. You can define up to 128 port-forwarding rules to allow requests from an external network to reach devices on the internal network.

Parameter Name	Description
Port Start Range	Enter a port number to define the port or first port in the range of interest. <i>Range</i> : 0 through 65535
Port End Range	Enter the same port number to apply port forwarding to a single port, or enter a larger number to apply it to a range of ports. <i>Range</i> : 0 through 65535
Protocol	Select the protocol to which to apply the port-forwarding rule, either TCP or UDP. To match the same ports for both TCP and UDP traffic, configure two rules.
VPN	Specify the private VPN in which the internal server resides. This VPN is one of the VPN identifiers in the overlay network. <i>Range</i> : 0 through 65530
Private IP	Specify the IP address of the internal server to which to direct traffic that matches the port-forwarding rule.

To save a port forwarding rule, click Add.

To save the feature template, click Save.

## Apply Access Lists

To apply a rewrite rule, access lists, and policers to a router interface, select the ACL tab and configure the following parameters:

Parameter Name	Description
Shaping rate	Configure the aggregate traffic transmission rate on the interface to be less than line rate, in kilobits per second (kbps).
QoS map	Specify the name of the QoS map to apply to packets being transmitted out the interface.
Rewrite Rule	Click On, and specify the name of the rewrite rule to apply on the interface.

Ingress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being received on the interface.
Egress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being transmitted on the interface.
Ingress ACL – IPv6	Click On, and specify the name of the access list to apply to IPv6 packets being received on the interface.
Egress ACL – IPv6	Click On, and specify the name of the access list to apply to IPv6 packets being transmitted on the interface.
Ingress Policer	Click On, and specify the name of the policer to apply to packets being received on the interface.
Egress Policer	Click On, and specify the name of the policer to apply to packets being transmitted on the interface.

To save the feature template, click Save.

## Configure Other Interface Properties

To configure other interface properties, select the Advanced tab and configure the following properties:

Parameter Name	Description
Bandwidth Upstream	For transmitted traffic, set the bandwidth above which to generate notifications. <i>Range:</i> 1 through (2 <sup>32</sup> / 2) – 1 kbps
Bandwidth Downstream	For received traffic, set the bandwidth above which to generate notifications. <i>Range:</i> 1 through (2 <sup>32</sup> / 2) – 1 kbps
IP MTU	Specify the maximum MTU size of packets on the interface. <i>Range:</i> 576 through 1804 <i>Default:</i> 1500 bytes
TCP MSS	Specify the maximum segment size (MSS) of TCP SYN packets passing through the router. By default, the MSS is dynamically adjusted based on the interface or tunnel MTU such that TCP SYN packets are never fragmented. <i>Range:</i> 552 to 1460 bytes <i>Default:</i> None
Clear Dont Fragment	Click On to clear the Don't Fragment bit in the IPv4 packet header for packets being transmitted out the interface. When the DF bit is cleared, packets larger than that interface's MTU are fragmented before being sent.
TLOC Extension	Enter the name of the physical interface on the same router that connects to the WAN transport circuit. This configuration then binds this service-side interface to the WAN transport. A second router at the same site that itself has no direct connection to the WAN (generally because the site has only a single WAN connection) and that connects to this service-side interface is then provided with a connection to the WAN.
Tracker	Enter the name of a tracker to track the status of transport interfaces that connect to the internet.

To save the feature template, click Save.

## Release Information

Introduced in vManage NMS in Release 18.3.

## VPN Interface Ethernet

Use the VPN Interface Ethernet template for all Viptela devices and Cisco IOS XE routers running the SD-WAN software.

---


## Configuration

To configure the Ethernet interfaces in a VPN using vManage templates:

1. Create a VPN Interface Ethernet feature template to configure Ethernet interface parameters, as described in this article.
2. Create a VPN feature template to configure VPN parameters. See the [VPN](#) help topic.
3. Optionally, on vEdge routers, to enable DHCP server functionality on the interface, create a DHCP Server feature template. See the [DHCP Server](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. To create a template for VPN 0 or VPN 512:
  - a. Click the Transport & Management VPN tab located directly beneath the Description field, or scroll to the Transport & Management VPN section.
  - b. Under Additional VPN 0 Templates, located to the right of the screen, click VPN Interface.
  - c. From the VPN Interface drop-down, click Create Template. The VPN Interface Ethernet template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN Interface Ethernet parameters.
6. To create a template for VPNs 1 through 511, and 513 through 65530:
  - a. Click the Service VPN tab located directly beneath the Description field, or scroll to the Service VPN section.
  - b. Click the Service VPN drop-down.
  - c. Under Additional VPN templates, located to the right of the screen, click VPN Interface.
  - d. From the VPN Interface drop-down, click Create Template. The VPN Interface Ethernet template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN Interface Ethernet parameters.



7. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
8. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <a href="#">attach a Viptela device to a device template</a> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>



## Configure Basic Interface Functionality

To configure basic interface functionality in a VPN, select the Basic Configuration tab and configure the following parameters. Parameters marked with an asterisk are required to configure an interface.

Parameter Name	Description
Shutdown*	Click No to enable the interface.
Interface name*	Enter a name for the interface.  For IOS XE routers, you must spell out the interface names completely (for example, <b>GigabitEthernet0/0/0</b> ), and you must configure all the router's interfaces even if you are not using them so that they are configured in the shutdown state and so that all default values for them are configured.
Description	Enter a description for the interface.
IPv4 Configuration*	To configure a static address, click Static and enter an IPv4 address.  To set the interface as a DHCP client so that the interface to receive its IP address from a DHCP server, click Dynamic. You can optionally set the DHCP distance to specify the administrative distance of routes learned from a DHCP server. The default DHCP distance is 1.
IPv6 Address*	To configure a static address for an interface in VPN 0, click Static and enter an IPv6 address.  To set the interface as a DHCP client so that the interface to receive its IP address from a DHCP server, click Dynamic. You can optionally set the DHCP distance to specify the administrative distance of routes learned from a DHCP server. The default DHCP distance is 1. You can optionally enable DHCP rapid commit, to speed up the assignment of IP addresses.
DHCP Helper (on vEdge routers)	Enter up to eight IP addresses for DHCP servers in the network, separated by commas, to have the interface be a DHCP helper. A DHCP helper interface forwards BOOTP (Broadcast) DHCP requests that it receives from the specified DHCP servers.
Block Non-Source IP (on vEdge routers)	Click Yes to have the interface forward traffic only if the source IP address of the traffic matches the interface's IP prefix range.
Bandwidth Upstream (on vEdge routers and vManage NMSs)	For transmitted traffic, set the bandwidth above which to generate notifications. <i>Range: 1 through (2<sup>32</sup> / 2) – 1 kbps</i>
Bandwidth Downstream (on vEdge routers and vManage NMSs)	For received traffic, set the bandwidth above which to generate notifications. <i>Range: 1 through (2<sup>32</sup> / 2) – 1 kbps</i>
Secondary IP Address (on vEdge routers)	Click Add to configure up to four secondary IPv4 addresses for a service-side interface.

To save the feature template, click Save.

### CLI equivalent:

```
vpn vpn-id
  interface interface-name
    bandwidth-downstream kbps
    bandwidth-upstream kbps
    block-non-source-ip
    description text
    dhcp-helper ip-address (on vEdge routers only)
    (ip address ipv4-prefix/length | ip dhcp-client [dhcp-distance number])
    (ipv6 address ipv6-prefix/length | ipv6 dhcp-client [dhcp-distance number] [dhcp-rapid-commit])
```

## Configuration

```
secondary-address ipv4-address
[no] shutdown
```

## Create a Tunnel Interface

On vEdge routers, you can configure up to four tunnel interfaces. This means that each vEdge router can have up to four TLOCs.

On vSmart controllers and vManage NMSs, you can configure one tunnel interface.

For the control plane to establish itself so that the overlay network can function, you must configure WAN transport interfaces in VPN 0.

To configure a tunnel interface, select the Interface Tunnel tab and configure the following parameters:

Parameter Name	Description
Tunnel Interface	Click On to create a tunnel interface.
Color	Select a color for the TLOC.
Control Connection (on vEdge routers)	If the vEdge router has multiple TLOCs, click No to have the tunnel not establish a TLOC. The default is On, which establishes a control connection for the TLOC.
Maximum Control Connections (on vEdge routers)	Specify the maximum number of vSmart controllers that the WAN tunnel interface can connect to. To have the tunnel establish no control connections, set the number to 0.  <i>Range: 0 through 8</i> <i>Default: 2</i>
vBond As Stun Server (on vEdge routers)	Click On to enable Session Traversal Utilities for NAT (STUN) to allow the tunnel interface to discover its public IP address and port number when the vEdge router is located behind a NAT.
Exclude Controller Group List (on vEdge routers)	Set the vSmart controllers that the tunnel interface is not allowed to connect to. <i>Range: 0 through 100</i>
vManage Connection Preference (on vEdge routers)	Set the preference for using a tunnel interface to exchange control traffic with the vManage NMS. <i>Range: 0 through 8</i> <i>Default: 5</i>
Port Hop	Click On to enable port hopping, or click Off to disable it. If port hopping is enabled globally, you can disable it on an individual TLOC (tunnel interface). To control port hopping on a global level, use the <a href="#">System</a> configuration template. <i>Default: Enabled (on vEdge routers); disabled (on vManage NMSs and vSmart controllers)</i>
Low-Bandwidth Link (on vEdge routers)	Select to characterize the tunnel interface as a low-bandwidth link.
Allow Service	Select On or Off for each service to allow or disallow the service on the interface.

To configure additional tunnel interface parameters, click Advanced Options:

Parameter Name	Description
GRE (on vEdge routers)	Use GRE encapsulation on the tunnel interface. By default, GRE is disabled.  If you select both IPsec and GRE encapsulations, two TLOCs are created for the tunnel interface that have the same IP addresses and colors, but that differ by their encapsulation.
IPsec (on vEdge routers)	Use IPsec encapsulation on the tunnel interface. By default, IPsec is enabled.  If you select both IPsec and GRE encapsulations, two TLOCs are created for the tunnel interface that have the same IP addresses and colors, but that differ by their encapsulation.

## Configuration

IPsec Preference (on vEdge routers)	Specify a preference value for directing traffic to the tunnel. A higher value is preferred over a lower value. <i>Range:</i> 0 through 4294967295 <i>Default:</i> 0
IPsec Weight (on vEdge routers)	Enter a weight to use to balance traffic across multiple TLOCs. A higher value sends more traffic to the tunnel. <i>Range:</i> 1 through 255 <i>Default:</i> 1
Carrier	Select the carrier name or private network identifier to associate with the tunnel. <i>Values:</i> carrier1, carrier2, carrier3, carrier4, carrier5, carrier6, carrier7, carrier8, default <i>Default:</i> default
Bind Loopback Tunnel (on vEdge routers)	Enter the name of a physical interface to bind to a loopback interface.
Last-Resort Circuit (on vEdge routers)	Select to use the tunnel interface as the circuit of last resort.
NAT Refresh Interval	Enter the interval between NAT refresh packets sent on a DTLS or TLS WAN transport connection. <i>Range:</i> 1 through 60 seconds <i>Default:</i> 5 seconds
Hello Interval	Enter the interval between Hello packets sent on a DTLS or TLS WAN transport connection. <i>Range:</i> 100 through 10000 milliseconds <i>Default:</i> 1000 milliseconds (1 second)
Hello Tolerance	Enter the time to wait for a Hello packet on a DTLS or TLS WAN transport connection before declaring that transport tunnel to be down. <i>Range:</i> 12 through 60 seconds <i>Default:</i> 12 seconds

To save the feature template, click Save.

*CLI equivalent:*

```
vpn 0
  interface interface-name
    tunnel-interface
      allow-service service-name
      bind interface-name (on vEdge routers only)
      carrier carrier-name
      color color
      encapsulation (gre | ipsec) (on vEdge routers only)
        preference number
        weight number
      exclude-controller-group-list number (on vEdge routers only)
      hello-interval milliseconds
      hello-tolerance seconds
      last-resort-circuit (on vEdge routers only)
      low-bandwidth-link (on vEdge routers only)
      max-control-connections number (on vEdge routers only)
      nat-refresh-interval seconds
      vbond-as-stun-server
      vmanage-connection-preference number (on vEdge routers only)
```

## Configure the Interface as a NAT Device (on vEdge Routers)

To configure an interface to act as a NAT device for applications such as port forwarding, select the NAT tab, click On and configure the following parameters:

Parameter Name	Description
NAT	Click On to have the interface act as a NAT device.
Refresh Mode	Select how NAT mappings are refreshed, either outbound or bidirectional (outbound and inbound). <i>Default : Outbound</i>
UDP Timeout	Specify when NAT translations over UDP sessions time out. <i>Range : 1 through 65536 minutes</i> <i>Default : 1 minutes</i>
TCP Timeout	Specify when NAT translations over TCP sessions time out. <i>Range : 1 through 65536 minutes</i> <i>Default : 60 minutes (1 hour)</i>
Block ICMP	Select On to block inbound ICMP error messages. By default, a vEdge router acting as a NAT device receives these error messages. <i>Default : Off</i>
Respond to Ping	Select On to have the vEdge router respond to ping requests to the NAT interface's IP address that are received from the public side of the connection.

To create a port forwarding rule, click Add New Port Forwarding Rule and configure the following parameters. You can define up to 128 port-forwarding rules to allow requests from an external network to reach devices on the internal network.

Parameter Name	Description
Port Start Range	Enter a port number to define the port or first port in the range of interest. <i>Range: 0 through 65535</i>
Port End Range	Enter the same port number to apply port forwarding to a single port, or enter a larger number to apply it to a range of ports. <i>Range: 0 through 65535</i>
Protocol	Select the protocol to which to apply the port-forwarding rule, either TCP or UDP. To match the same ports for both TCP and UDP traffic, configure two rules.
VPN	Specify the private VPN in which the internal server resides. This VPN is one of the VPN identifiers in the overlay network. <i>Range: 0 through 65530</i>
Private IP	Specify the IP address of the internal server to which to direct traffic that matches the port-forwarding rule.

To save a port forwarding rule, click Add.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
 interface interface-name
   nat
     block-icmp-error
     port-forward port-start port-number1 port-end port-number2 proto (tcp | udp)
       private-ip-address ip-address private-vpn vpn-id
     refresh (bi-directional | outbound)
     respond-to-ping
```

## Configuration

```

tcp-timeout minutes
udp-timeout minutes

```

## Configure VRRP (on vEdge Routers)

To have an interface run the Virtual Router Redundancy Protocol (VRRP), which allows multiple routers to share a common virtual IP address for default gateway redundancy, select the VRRP tab. Then click Add New VRRP and configure the following parameters:

Parameter Name	Description
Group ID	Enter the virtual router ID, which is a numeric identifier of the virtual router. You can configure a maximum of 24 groups. <i>Range:</i> 1 through 255
Priority	Enter the priority level of the router. The router with the highest priority is elected as primary. If two vEdge routers have the same priority, the one with the higher IP address is elected as primary. <i>Range:</i> 1 through 254 <i>Default:</i> 100
Timer	Specify how often the VRRP primary sends VRRP advertisement messages. If secondary routers miss three consecutive VRRP advertisements, they elect a new primary. <i>Range:</i> 1 through 3600 seconds <i>Default:</i> 1 second
Track OMP Track Prefix List	By default, VRRP uses the state of the service (LAN) interface on which it is running to determine which vEdge router is the primary virtual router. If a vEdge router loses all its WAN control connections, the LAN interface still indicates that it is up even though the router is functionally unable to participate in VRRP. To take WAN side connectivity into account for VRRP, configure one of the following:  Track OMP—Click On for VRRP to track the Overlay Management Protocol (OMP) session running on the WAN connection. If the primary VRRP router loses all its OMP sessions, VRRP elects a new default gateway from those that have at least one active OMP session.  Track Prefix List—Track both the OMP session and a list of remote prefixes, which is defined in a prefix list configured on the local router. If the primary VRRP router loses all its OMP sessions, VRRP failover occurs as described for the Track OMP option. In addition, if reachability to one of the prefixes in the list is lost, VRRP failover occurs immediately, without waiting for the OMP hold timer to expire, thus minimizing the amount of overlay traffic is dropped while the vEdge routers determine the VRRP primary.
IP Address	Enter the IP address of the virtual router. This address must be different from the configured interface IP addresses of both the local vEdge router and the peer running VRRP.

*CLI equivalent:*

```

vpn vpn-id
  interface geslot/port[.subinterface]
    vrrp group-number
      ipv4 ip-address
      priority number
      timer seconds
      (track-omp | track-prefix-list list-name)

```

## Apply Access Lists and QoS Parameters (on vEdge Routers)

To configure a shaping rate to a router interface and to apply a QoS map, a rewrite rule, access lists, and policers to a router interface, select the ACL/QoS tab and configure the following parameters:

Parameter Name	Description
----------------	-------------

## Configuration

Shaping rate	Configure the aggregate traffic transmission rate on the interface to be less than line rate, in kilobits per second (kbps).
QoS Map	Specify the name of the QoS map to apply to packets being transmitted out the interface.
Rewrite Rule	Click On, and specify the name of the rewrite rule to apply on the interface.
Ingress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being received on the interface.
Egress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being transmitted on the interface.
Ingress ACL – IPv6	Click On, and specify the name of the access list to apply to IPv6 packets being received on the interface.
Egress ACL – IPv6	Click On, and specify the name of the access list to apply to IPv6 packets being transmitted on the interface.
Ingress Policer	Click On, and specify the name of the policer to apply to packets received on the interface.
Egress Policer	Click On, and specify the name of the policer to apply to packets being transmitted on the interface.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  interface interface-name
    access-list acl-list (in | out)
    policer policer-name (in |out)
    qos-map name
    rewrite-rule name
    shaping-rate name
```

## Add ARP Table Entries

To configure static Address Resolution Protocol (ARP) table entries on the interface, select the ARP tab. Then click Add New ARP and configure the following parameters:

Parameter Name	Description
IP Address	Enter the IP address for the ARP entry in dotted decimal notation or as a fully qualified host name.
MAC Address	Enter the MAC address in colon-separated hexadecimal notation.

To save the ARP configuration, click Add.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  interface interface-name
    arp
      ip ip-address mac mac-address
```

## Configure IEEE 802.1X Authentication for WANs

To configure IEEE 802.1X authentication for WANs on the interface, select the 802.1X tab, and click On:

Parameter Name	Description
----------------	-------------

802.1X	Click On to enable IEEE 802.1X on the interface.
RADIUS Server	Enter the tag of the RADIUS server to use for 802.1X authentication. It can be from 4 through 16 characters long. You configure the tag in the <a href="#">AAA feature template</a> .
Account Interim Interval	Enter how often to send 802.1X interim accounting updates to the RADIUS server. <i>Range:</i> 0 through 7200 seconds <i>Default:</i> 0 (no interim accounting updates are sent)
NAS Identifier	Enter the NAS identifier of the local router. It can be a string from 1 to 255 characters long. This identifier is sent to the RADIUS server.
NAS IP	Enter the NAS IP address of the local router. This address is sent to the RADIUS server.
Wake On LAN	Enable a client to be powered up when the router receives an Ethernet magic packet frame.
Control Direction	Select how an 802.1X interface that is using wake on LAN handles packets from unauthorized clients: <ul style="list-style-type: none"> <li>In and Out—Send and receive packets with unauthorized clients. This is the default</li> <li>In Only—Send but do not receive packets with unauthorized clients.</li> </ul>
Reauthentication	Enter how often to reauthenticate 802.1X clients. By default, no reauthentication attempts are made after the initial LAN access request. <i>Range:</i> 0 through 1440 minutes
Inactivity	Enter how long to wait before revoking an 802.1X client's network access. <i>Range:</i> 0 through 1440 minutes (24 hours) <i>Default:</i> 60 minutes (1 hour)
Host Mode	Select whether an 802.1X interface grants access to a single client or to multiple clients: <ul style="list-style-type: none"> <li>Multi Auth—Grant access to one client on a voice VLAN and multiple clients on data VLANs.</li> <li>Multi Host—Grant access to multiple clients</li> <li>Single Host—Grant access only to the first authenticated client. This is the default.</li> </ul>

To configure other IEEE 802.1X authentication properties, click Advanced Options and configure the following parameters:

#### Parameter Name

#### Description

#### Authentication Order

Set the order of authentication methods to use when authenticating devices for connection to the 802.1X WAN. The default authentication order is RADIUS, then MAC authentication bypass (MAB).

#### VLAN

#### Authentication Fail VLAN

Configure network access when RADIUS authentication or the RADIUS server fails. An authentication-fail VLAN is similar to a critical VLAN.

#### Guest VLAN

Configure a guest VLAN to provide limited services to 802.1X-compliant clients.

#### Authentication Reject VLAN

Configure limited services to 802.1X-compliant clients that failed RADIUS authentication. An authentication-reject VLAN is similar to a restricted VLAN.

### Default VLAN

Configure network access for 802.1X-compliant clients that are successfully authenticated by the RADIUS server. If you do not configure a default VLAN on the router, successfully authenticated clients are placed into VLAN 0, which is the VLAN associated with an untagged bridge.

### Dynamic Authentication Server

#### DAS Port

Configure the UDP port number to listen for CoA requests from the RADIUS server.

*Range:* 1 through 65535

*Default:* 3799

#### Client

Set the IP address of the RADIUS or other authentication server from which to accept CoA requests.

#### Secret Key

Set the password that the RADIUS or other authentication server uses to access the router's 802.1X interface.

#### Time Window

Set how long a CoA request is valid.

*Range:* 0 through 1000 seconds

*Default:* 300 seconds (5 minutes)

#### Require Timestamp

Enable to require the DAS client to timestamp CoA messages.

#### VPN

Set the VPN through which the RADIUS or other authentication server is reachable.

### MAC Authentication Bypass

#### Server

Select to enable MAC authentication bypass (MAB) on the RADIUS server and to authentication non-802.1X-compliant clients using a RADIUS server.

#### Allow

Specify the MAC addresses of one or more devices so that authentication checks for these devices are performed using the RADIUS server.

### Request Attributes

#### Authentication

Click Authentication, then click Add New Authentication Entry to configure RADIUS authentication attribute-value (AV) pairs to send to the RADIUS server during an 802.1X session.

To save the entry, click Add.

#### Accounting

Click Accounting, then click Add New Accounting Entry to configure RADIUS accounting attribute-value (AV) pairs to send to the RADIUS server during an 802.1X session.

To save the entry, click Add.



## Configuration

To save the feature template, click Save.

*CLI equivalent:*

```

vpn 0
 interface interface-name
   dot1x
     accounting-interval minutes
     acct-req-attr attribute-number (integer integer | octet octet | string string)
     auth-fail-vlan vlan-id
     auth-order (mab | radius)
     auth-reject-vlan vlan-id
     auth-req-attr attribute-number (integer integer | octet octet | string string)
     control-direction direction
     das
       client ip-address
       port port-number
       require-timestamp
       secret-key password
       time-window seconds
       vpn vpn-id
     default-vlan vlan-id
     guest-vlan vlan-id
     host-mode (multi-auth | multi-host | single-host)
     mac-authentication-bypass
       allow mac-addresses
       server
     nas-identifier string
     nas-ip-address ip-address
     radius-servers tag
     reauthentication minutes
     timeout
       inactivity minutes
     wake-on-lan

```

## Configure Other Interface Properties

To configure other interface properties, select the Advanced tab and configure the following parameters:

Parameter Name	Description
Duplex	Choose full or half to specify whether the interface runs in full-duplex or half-duplex mode. <i>Default:</i> full
MAC Address	Specify a MAC address to associate with the interface, in colon-separated hexadecimal notation.
IP MTU	Specify the maximum MTU size of packets on the interface. <i>Range:</i> 576 through 1804 <i>Default:</i> 1500 bytes
PMTU Discovery	Click On to enable path MTU discovery on the interface. PMTU determines the largest MTU size that the interface supports so that packet fragmentation does not occur.
Flow Control	Select a setting for bidirectional flow control, which is a mechanism for temporarily stopping the transmission of data on the interface. <i>Values:</i> autonet, both, egress, ingress, none <i>Default:</i> autoneg

TCP MSS	Specify the maximum segment size (MSS) of TCP SYN packets passing through the router. By default, the MSS is dynamically adjusted based on the interface or tunnel MTU such that TCP SYN packets are never fragmented. <i>Range:</i> 552 to 1460 bytes <i>Default:</i> None
Speed	Specify the speed of the interface, for use when the remote end of the connection does not support autonegotiation. <i>Values:</i> 10, 100, or 1000 Mbps <i>Default:</i> Autonegotiate (10/100/1000 Mbps)
Clear-Dont-Fragment	Click On to clear the Don't Fragment (DF) bit in the IPv4 packet header for packets being transmitted out the interface. When the DF bit is cleared, packets larger than that interface's MTU are fragmented before being sent.
Static Ingress QoS (on vEdge routers)	Specify a queue number to use for incoming traffic. <i>Range:</i> 0 through 7
ARP Timeout (on vEdge routers)	Specify how long it takes for a dynamically learned ARP entry to time out. <i>Range:</i> 0 through 2678400 seconds (744 hours) <i>Default:</i> 1200 (20 minutes)
Autonegotiation	Click Off to turn off autonegotiation. By default, an interface runs in autonegotiation mode.
TLOC Extension	Enter the name of a physical interface on the same router that connects to the WAN transport. This configuration then binds this service-side interface to the WAN transport. A second router at the same site that itself has no direct connection to the WAN (generally because the site has only a single WAN connection) and that connects to this service-side interface is then provided with a connection to the WAN.  Note that TLOC extension over L3 is only supported for Cisco IOS XE routers. If configuring TLOC extension over L3 for a Cisco IOS XE router, enter the IP address of the L3 interface.
Power over Ethernet (on vEdge 100m and vEdge 100wm routers)	Click On to enable PoE on the interface.
Tracker (on vEdge routers)	Enter the name of a tracker to track the status of transport interfaces that connect to the internet.
ICMP Redirect (on vEdge routers)	Click Disable to disable ICMP redirect messages on the interface. By default, an interface allows ICMP redirect messages.
GRE Tunnel Source IP (on IOS XE routers)	Enter the IP address of the extended WAN interface.
Xconnect (on IOS XE routers)	Enter the name of a physical interface on the same router that connects to the WAN transport.

**CLI equivalent:**

```

vpn vpn-id
  interface interface-name
    arp-timeout seconds (on vEdge routers only)
    [no] autonegotiate
    clear-dont-fragment
    duplex (full | half)
    flow-control control
    icmp-redirect-disable (on vEdge routers only)
    mac-address mac-address
    mtu bytes
    pmtu
    pppoe-client (on vEdge 100m and vEdge 100wm routers only)
    ppp-interface pppnumber

```

---

## Configuration

```
speed speed
static-ingress-qos number (on vEdge routers only)
tcp-mss-adjust bytes
tloc-extension interface-name (on vEdge routers only)
tracker tracker-name (on vEdge routers only)
```

## Release Information

Introduced in vManage NMS Release 15.2.

In Release 17.2.2, add support for tracker interface status.

In Release 18.2, add support for disabling ICMP redirect messages.

## VPN Interface GRE

Use the VPN Interface GRE template for all vEdge Cloud and vEdge router devices.

When a service, such as a firewall, is available on a device that supports only GRE tunnels, you can configure a GRE tunnel on the vEdge router to connect to the remote device by configuring a logical GRE interface. You then advertise that the service is available via a GRE tunnel, and you create data policies to direct the appropriate traffic to the tunnel. GRE interfaces come up as soon as they are configured, and they stay up as long as the physical tunnel interface is up.


To configure GRE interfaces using vManage templates:

1. Create a VPN Interface GRE feature template to configure a GRE interface, as described in this article.
2. Create a VPN feature template to advertise a service that is reachable via a GRE tunnel, to configure GRE-specific static routes, and to configure other VPN parameters. See the [VPN](#) help topic.
3. Create a data policy on the vSmart controller that applies to the service VPN, including a **set service service-name local** command. See the [Policies](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. To create a template for VPN 0 or VPN 512:
  - a. Click the Transport & Management VPN tab located directly beneath the Description field, or scroll to the Transport & Management VPN section.
  - b. Under Additional VPN 0 Templates, located to the right of the screen, click VPN Interface GRE.
  - c. From the VPN Interface GRE drop-down, click Create Template. The VPN Interface GRE template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN Interface GRE parameters.
6. To create a template for VPNs 1 through 511, and 513 through 65530:
  - a. Click the Service VPN tab located directly beneath the Description field, or scroll to the Service VPN section.
  - b. Click the Service VPN drop-down.
  - c. Under Additional VPN templates, located to the right of the screen, click VPN Interface GRE.

- d. From the VPN Interface GRE drop-down, click Create Template. The VPN Interface GRE template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN Interface GRE parameters.



- 7. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
- 8. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>

Global (indicated by a globe icon)	Enter a value for the parameter, and apply that value to all devices.  Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.
------------------------------------	--

## Configuring a Basic GRE Interface

To configure a basic GRE interface, select the Basic Configuration and then configure the following parameters. Parameters marked with an asterisk are required to configure a GRE interface.

Parameter Name	Description
Shutdown*	Click Off to enable the interface.
Interface Name*	Enter the name of the GRE interface, in the format <b>gre number</b> . <i>number</i> can be from 1 through 255.
Description	Enter a description of the GRE interface.
Source*	Enter the source of the GRE interface: <ul style="list-style-type: none"> <li>GRE Source IP Address—Enter the source IP address of the GRE tunnel interface. This address is on the local router.</li> <li>Tunnel Source Interface—Enter the physical interface that is the source of the GRE tunnel.</li> </ul>
Destination*	Enter the destination IP address of the GRE tunnel interface. This address is on a remote device
GRE Destination IP Address*	Enter the destination IP address of the GRE tunnel interface. This address is on a remote device
IPv4 Address	Enter an IPv4 address for the GRE tunnel.
IP MTU	Specify the maximum MTU size of packets on the interface. <i>Range:</i> 576 through 1804 <i>Default:</i> 1500 bytes
Clear-Don't-Fragment	Click On to clear the Don't Fragment bit in the IPv4 packet header for packets being transmitted out the interface.
TCP MSS	Specify the maximum segment size (MSS) of TCP SYN packets passing through the vEdge router. By default, the MSS is dynamically adjusted based on the interface or tunnel MTU such that TCP SYN packets are never fragmented. <i>Range:</i> 552 to 1460 bytes <i>Default:</i> None
Keepalive Interval	Specify how often the GRE interface sends keepalive packets on the GRE tunnel. Because GRE tunnels are stateless, sending of keepalive packets is the only way to determine whether the remote end of the tunnel is up. The keepalive packets are looped back to the sender. Receipt of these packets by the sender indicates that the remote end of the GRE tunnel is up. <i>Range:</i> 0 through 65535 seconds <i>Default:</i> 10 seconds
Keepalive Retries	Specify how many times the GRE interface tries to resend keepalive packets before declaring the remote end of the GRE tunnel to be down. <i>Range:</i> 0 through 255 <i>Default:</i> 3

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  interface grenumber
```

## Configuration

```

clear-dont-fragment
description text
ip address ipv4-prefix/length
keepalive seconds retries
mtu bytes
policer policer-name (in |out)
qos-map name
rewrite-rule name
shaping-rate name
[no] shutdown
tcp-mss-adjust bytes
tunnel-destination ip-address
(tunnel-source ip-address | tunnel-source-interface interface-name)

```

## Configure Interface Access Lists

To configure access lists on a GRE interface, select the ACL tab and configure the following parameters:

Parameter Name	Description
Rewrite Rule	Click On, and specify the name of the rewrite rule to apply on the interface.
Ingress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being received on the interface.
Egress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being transmitted on the interface.
Ingress Policer	Click On, and specify the name of the policer to apply to packets being received on the interface.
Egress Policer	Click On, and specify the name of the policer to apply to packets being transmitted on the interface.

*CLI equivalent:*

```

vpn vpn-id
interface grenumber
access-list acl-list (in | out)
policer policer-name (in |out)
qos-map name
rewrite-rule name
shaping-rate name

```

## Release Information

Introduced in vManage NMS Release 15.4.1.

## VPN Interface IPsec for vEdge Routers


Use the VPN Interface IPsec feature template to configure IPsec tunnels on vEdge routers that are being used for Internet Key Exchange (IKE) sessions. You can configure IPsec on tunnels in the transport VPN (VPN 0) and in service VPNs (VPN 1 through 65530, except for 512).

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.

Configuration

5. Click the Service VPN tab located directly beneath the Description field, or scroll to the Service VPN section.
6. Click the Service VPN drop-down.



7. Under Additional VPN Templates, located to the right of the screen, click VPN Interface IPsec.
8. From the VPN Interface IPsec drop-down, click Create Template. The VPN Interface IPsec template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN Interface IPsec parameters.
9. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
10. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>

Global (indicated by a globe icon)	Enter a value for the parameter, and apply that value to all devices.  Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.
------------------------------------	--

## Configure a Basic IPsec Tunnel Interface

To configure an IPsec tunnel to use for IKE sessions, select the Basic Configuration tab and configure the following parameters. Parameters marked with an asterisk are required to configure an IPsec tunnel.

Parameter Name	Description
Shutdown*	Click No to enable the interface.
Interface Name*	Enter the name of the IPsec interface, in the format <b>ipsec number . number</b> . number can be from 1 through 256.
Description	Enter a description of the IPsec interface.
IPv4 Address*	Enter the IPv4 address of the IPsec interface, in the format <i>IPv4-prefix / length</i> . The address must be a /30.
Source*	Set the source of the IPsec tunnel that is being used for IKE key exchange: <ul style="list-style-type: none"> <li>Click IP Address—Enter the IPv4 address that is the source tunnel interface. This address must be configured in VPN 0.</li> <li>Click Interface—Enter the name of the physical interface that is the source of the IPsec tunnel. This interface must be configured in VPN 0.</li> </ul>
Destination: IPsec Destination IP Address/FQDN*	Set the destination of the IPsec tunnel that is being used for IKE key exchange. Enter either an IPv4 address or the fully qualified DNS name that points to the destination.
TCP MSS	Specify the maximum segment size (MSS) of TCP SYN packets passing through the vEdge router. By default, the MSS is dynamically adjusted based on the interface or tunnel MTU such that TCP SYN packets are never fragmented. <i>Range:</i> 552 to 1460 bytes <i>Default:</i> None
IP MTU	Specify the maximum MTU size of packets on the interface. <i>Range:</i> 576 through 1804 <i>Default:</i> 1500 bytes

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  interface ipsecnumber
    ip address ipv4-prefix/length
    mtu bytes
    no shutdown
    tcp-mss-adjust bytes
    tunnel-destination ipv4-address
    (tunnel-source ip-address | tunnel-source-interface interface-name)
```

## Configure Dead-Peer Detection

To configure IKE dead-peer detection to determine whether the connection to an IKE peer is functional and reachable, select the DPD tab and configure the following parameters:



## Configuration

Parameter Name	Description
DPD Interval	Specify the interval for IKE to send Hello packets on the connection. <i>Range:</i> 0 through 65535 seconds (1 hour through 14 days) <i>Default:</i> 10 seconds
DPD Retries	Specify how many unacknowledged packets to accept before declaring an IKE peer to be dead and then tearing down the tunnel to the peer. <i>Range:</i> 0 through 255 <i>Default:</i> 3

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
 interface ipsecnumber
   dead-peer-detection seconds retries number
```

## Configure IKE

To configure IKE, select the IKE tab and configure the parameters discussed below.

When you create an IPsec tunnel on a vEdge router, IKE Version 1 is enabled by default on the tunnel interface. The following properties are also enabled by default for IKEv1:

- Authentication and encryption—AES-256 advanced encryption standard CBC encryption with the HMAC-SHA1 keyed-hash message authentication code algorithm for integrity
- Diffie-Hellman group number—16
- Rekeying time interval—4 hours
- SA establishment mode—Main

To modify IKEv1 parameters, configure the following:

Parameter Name	Description
IKE Version	Enter 1 to select IKEv1.
IKE Mode	Specify the IKE SA establishment mode. <i>Values:</i> Aggressive mode, Main mode <i>Default:</i> Main mode
IPsec Rekey Interval	Specify the interval for refreshing IKE keys. <i>Range:</i> 3600 through 1209600 seconds (1 hour through 14 days) <i>Default:</i> 14400 seconds (4 hours)
IKE Cipher Suite	Specify the type of authentication and encryption to use during IKE key exchange. <i>Values:</i> aes128-cbc-sha1, aes256-cbc-sha1 <i>Default:</i> aes256-cbc-sha1
IKE Diffie-Hellman Group	Specify the Diffie-Hellman group to use in IKE key exchange. <i>Values:</i> 1024-bit modulus, 2048-bit modulus, 3072-bit modulus, 4096-bit modulus <i>Default:</i> 4096-bit modulus
IKE Authentication: Preshared Key	To use preshared key (PSK) authentication, enter the password to use with the preshared key.

## Configuration

IKE ID for Local End Point	If the remote IKE peer requires a local end point identifier, specify it. <i>Range: Default:</i> Tunnel's source IP address
IKE ID for Remote End Point	If the remote IKE peer requires a remote end point identifier, specify it. <i>Range:</i> 1 through 64 characters <i>Default:</i> Tunnel's destination IP address

To save the feature template, click Save.

**CLI equivalent:**

```
vpn vpn-id
  interface ipsecnumber
    ike
      authentication-type type
      local-id id
      pre-shared-secret password
      remote-id id
      cipher-suite suite
      group number
      mode mode
      rekey-interval seconds
      version 1
```

To configure IKEv2, configure the following parameters:

Parameter Name	Description
IKE Version	Enter 2 to select IKEv2.
IPsec Rekey Interval	Specify the interval for refreshing IKE keys. <i>Range:</i> 3600 through 1209600 seconds (1 hour through 14 days) <i>Default:</i> 14400 seconds (4 hours)
IKE Cipher Suite	Specify the type of authentication and encryption to use during IKE key exchange. <i>Values:</i> aes128-cbc-sha1, aes256-cbc-sha1 <i>Default:</i> aes256-cbc-sha1
IKE Diffie-Hellman Group	Specify the Diffie-Hellman group to use in IKE key exchange. <i>Values:</i> 1024-bit modulus, 2048-bit modulus, 3072-bit modulus, 4096-bit modulus <i>Default:</i> 4096-bit modulus
IKE Authentication: Preshared Key	To use preshared key (PSK) authentication, enter the password to use with the preshared key.
IKE ID for Local End Point	If the remote IKE peer requires a local end point identifier, specify it. <i>Range: Default:</i> Tunnel's source IP address
IKE ID for Remote End Point	If the remote IKE peer requires a remote end point identifier, specify it. <i>Range:</i> 1 through 64 characters <i>Default:</i> Tunnel's destination IP address

To save the feature template, click Save.

**CLI equivalent:**

```
vpn vpn-id
  interface ipsecnumber
    ike
      authentication-type type
      local-id id
      pre-shared-secret password
      remote-id id
      cipher-suite suite
```

## Configuration

```

group number
rekey-interval seconds
version 2

```

## Configure IPsec Tunnel Parameters

To configure the IPsec tunnel that carries IKE traffic, select the IPsec tab and configure the following parameters:

Parameter Name	Description
IPsec Rekey Interval	Specify the interval for refreshing IKE keys. <i>Range:</i> 3600 through 1209600 seconds (1 hour through 14 days) <i>Default:</i> 14400 seconds (4 hours)
IKE Replay Window	Specify the replay window size for the IPsec tunnel. <i>Values:</i> 64, 128, 256, 512, 1024, 2048, 4096, 8192 bytes <i>Default:</i> 32 bytes
IPsec Cipher Suite	Specify the authentication and encryption to use on the IPsec tunnel. <i>Values:</i> <b>aes256-cbc-sha1</b> , <b>aes256-gcm</b> , <b>null-sha1</b> <i>Default:</i> <b>aes256-gcm</b>
Perfect Forward Secrecy	Specify the PFS settings to use on the IPsec tunnel. <i>Values:</i> <ul style="list-style-type: none"> <li>• <b>group-2</b> —Use the 1024-bit Diffie-Hellman prime modulus group.</li> <li>• <b>group-14</b> —Use the 2048-bit Diffie-Hellman prime modulus group.</li> <li>• <b>group-15</b> —Use the 3072-bit Diffie-Hellman prime modulus group.</li> <li>• <b>group-16</b> —Use the 4096-bit Diffie-Hellman prime modulus group.</li> <li>• <b>none</b> —Disable PFS.</li> </ul> <i>Default:</i> <b>group-16</b>

To save the feature template, click Save.

### CLI equivalent:

```

vpn vpn-id
 interface ipsecnumber
   ipsec
     cipher-suite suite
     perfect-forward-secrecy pfs-setting
     rekey-interval seconds
     replay-window number

```

## Release Information

Introduced in vManage NMS in Release 17.2.

In Release 17.2.3, add support for PFS.

In Release 18.2, support support for IPsec tunnels in VPN 0.

## VPN Interface Multilink

Use the VPN Interface Multilink template for Cisco IOS XE routers running the SD-WAN software.


Multilink Point-to-Point Protocol (MLP) is used to combine multiple physical links into a single logical connection, called an MLP bundle.

To configure multilink on IOS XE routers using vManage templates:

1. Create a VPN Interface Multilink feature template to configure multilink interface properties.
2. Optionally, create a VPN feature template to modify the default configuration of VPN 0. See the [VPN](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. If you are configuring the multilink interface in the transport VPN (VPN 0):
  - a. Click the Transport & Management VPN tab located directly beneath the Description field, or scroll to the Transport & Management VPN section.
  - b. Under Additional VPN 0 Templates, located to the right of the screen, click VPN Interface Multilink Controller.
6. If you are configuring the multilink interface in a service VPN (VPNs other than VPN 0):
  - a. Click the Service VPN tab located directly beneath the Description field, or scroll to the Service VPN section.
  - b. In the Service VPN drop-down, enter the number of the service VPN.
  - c. Under Additional VPN Templates, located to the right of the screen, click VPN Interface Multilink Controller.
7. From the VPN Interface Multilink Controller drop-down, click Create Template. The VPN Multilink template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining multilink Interface parameters.



8. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.

## Configuration

9. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <a href="#">attach a Viptela device to a device template</a> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure a Multilink Interface

To configure a multilink interface, select the Basic Configuration tab and configure the following parameters. Parameters marked with an asterisk are required to configure the interface.

Note, if you are creating a VPN Interface Multilink template, you do not need to create a T1/E1 Controller template or a VPN Interface T1/E1 template.

Parameter Name	Description
Shutdown*	Click No to enable the multilink interface.
Multilink Interface Name*	Enter the number of the MLP interface. It can be a number from 1 through 65,535.
Description	Enter a description for the multilink interface.
Multilink Group Number*	Enter the number of the multilink group. It can be a number from 1 through 65,535 but it must be the same as the number you enter in the Multilink Interface Name parameter.
IPv4 Address*	<p>To configure a static address, click Static and enter an IPv4 address.</p> <p>To set the interface as a DHCP client so that the interface to receive its IP address from a DHCP server, click Dynamic. You can optionally set the DHCP distance to specify the administrative distance of routes learned from a DHCP server. The default DHCP distance is 1.</p>
IPv6 Address*	<p>To configure a static address for an interface in VPN 0, click Static and enter an IPv6 address.</p> <p>To set the interface as a DHCP client so that the interface to receive its IP address from a DHCP server, click Dynamic. You can optionally set the DHCP distance to specify the administrative distance of routes learned from a DHCP server. The default DHCP distance is 1. You can optionally enable DHCP rapid commit, to speed up the assignment of IP addresses.</p>

Bandwidth Upstream	For transmitted traffic, set the bandwidth above which to generate notifications. <i>Range:</i> 1 through $(2^{32} / 2) - 1$ kbps
Bandwidth Downstream	For received traffic, set the bandwidth above which to generate notifications. <i>Range:</i> 1 through $(2^{32} / 2) - 1$ kbps
IP MTU	Specify the maximum MTU size of packets on the interface. MLP encapsulation adds 6 extra bytes (4 header, 2 checksum) to each outbound packet. These overhead bytes reduce the effective bandwidth on the connection; therefore, the throughput for an MLP bundle is slightly less than an equivalent bandwidth connection that is not using MLP. <i>Range:</i> 576 through 1804 <i>Default:</i> 1500 bytes

To save the feature template, click Save.

## Configure the PPP Authentication Protocol

To configure the PPP authentication protocol, select the PPP tab and configure the following parameters:

Parameter Name	Description
Authentication Protocol	Select the authentication protocol used by the MLP: <ul style="list-style-type: none"> <li>CHAP—Enter the hostname and password provided by your Internet Service Provider (ISP). <i>hostname</i> can be up to 255 characters.</li> <li>PAP—Enter the username and password provided by your ISP. <i>username</i> can be up to 255 characters.</li> <li>PAP and CHAP—Configure both authentication protocols. Enter the login credentials for each protocol. To use the same username and password for both, click Same Credentials for PAP and CHAP.</li> </ul>

To save the feature template, click Save.

## Create a Tunnel Interface

On vEdge routers, you can configure up to four tunnel interfaces. This means that each vEdge router can have up to four TLOCs.

For the control plane to establish itself so that the overlay network can function, you must configure WAN transport interfaces in VPN 0.

To configure a tunnel interface for the multilink interface, select the Tunnel Interface tab and configure the following parameters:

Parameter Name	Description
Tunnel Interface	Click On to create a tunnel interface.
Color	Select a color for the TLOC.
Control Connection	If the vEdge router has multiple TLOCs, click No to have the tunnel not establish a TLOC. The default is On, which establishes a control connection for the TLOC.
Maximum Control Connections	Specify the maximum number of vSmart controllers that the WAN tunnel interface can connect to. To have the tunnel establish no control connections, set the number to 0. <i>Range:</i> 0 through 8 <i>Default:</i> 2
vBond As STUN Server	Click On to enable Session Traversal Utilities for NAT (STUN) to allow the tunnel interface to discover its public IP address and port number when the vEdge router is located behind a NAT.

## Configuration

Exclude Controller Group List	Set the vSmart controllers that the tunnel interface is not allowed to connect to. <i>Range:</i> 0 through 100
vManage Connection Preference	Set the preference for using a tunnel interface to exchange control traffic with the vManage NMS. <i>Range:</i> 0 through 8 <i>Default:</i> 5
Port Hop	Click On to enable port hopping, or click Off to disable it. When a router is behind a NAT, port hopping rotates through a pool of preselected OMP port numbers (called base ports) to establish DTLS connections with other routers when a connection attempt is unsuccessful. The default base ports are 12346, 12366, 12386, 12406, and 12426. To modify the base ports, set a port offset value. <i>Default:</i> Enabled
Low-Bandwidth Link	Select to characterize the tunnel interface as a low-bandwidth link.
Allow Service	Select On or Off for each service to allow or disallow the service on the interface.

To configure additional tunnel interface parameters, click Advanced Options and configure the following parameters:

Parameter Name	Description
GRE	Use GRE encapsulation on the tunnel interface. By default, GRE is disabled.  If you select both IPsec and GRE encapsulations, two TLOCs are created for the tunnel interface that have the same IP addresses and colors, but that differ by their encapsulation.
IPsec	Use IPsec encapsulation on the tunnel interface. By default, IPsec is enabled.  If you select both IPsec and GRE encapsulations, two TLOCs are created for the tunnel interface that have the same IP addresses and colors, but that differ by their encapsulation.
IPsec Preference	Specify a preference value for directing traffic to the tunnel. A higher value is preferred over a lower value. <i>Range:</i> 0 through 4294967295 <i>Default:</i> 0
IPsec Weight	Enter a weight to use to balance traffic across multiple TLOCs. A higher value sends more traffic to the tunnel. <i>Range:</i> 1 through 255 <i>Default:</i> 1
Carrier	Select the carrier name or private network identifier to associate with the tunnel. <i>Values:</i> carrier1, carrier2, carrier3, carrier4, carrier5, carrier6, carrier7, carrier8, default <i>Default:</i> default
Bind Loopback Tunnel	Enter the name of a physical interface to bind to a loopback interface.
Last-Resort Circuit	Select to use the tunnel interface as the circuit of last resort.
NAT Refresh Interval	Enter the interval between NAT refresh packets sent on a DTLS or TLS WAN transport connection. <i>Range:</i> 1 through 60 seconds <i>Default:</i> 5 seconds
Hello Interval	Enter the interval between Hello packets sent on a DTLS or TLS WAN transport connection. <i>Range:</i> 100 through 10000 milliseconds <i>Default:</i> 1000 milliseconds (1 second)

Hello Tolerance	Enter the time to wait for a Hello packet on a DTLS or TLS WAN transport connection before declaring that transport tunnel to be down.  <i>Range:</i> 12 through 60 seconds <i>Default:</i> 12 seconds
-----------------	---

## Apply Access Lists

To apply a rewrite rule, access lists, and policers to a router interface, select the ACL tab and configure the following parameters:

Parameter Name	Description
Shaping rate	Configure the aggregate traffic transmission rate on the interface to be less than line rate, in kilobits per second (kbps).
QoS map	Specify the name of the QoS map to apply to packets being transmitted out the interface.
Rewrite Rule	Click On, and specify the name of the rewrite rule to apply on the interface.
Ingress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being received on the interface.
Egress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being transmitted on the interface.
Ingress ACL – IPv6	Click On, and specify the name of the access list to apply to IPv6 packets being received on the interface.
Egress ACL – IPv6	Click On, and specify the name of the access list to apply to IPv6 packets being transmitted on the interface.
Ingress Policer	Click On, and specify the name of the policer to apply to packets being received on the interface.
Egress Policer	Click On, and specify the name of the policer to apply to packets being transmitted on the interface.

To save the feature template, click Save.

## Configure Other Interface Properties

To configure other interface properties, select the Advanced tab and configure the following properties:

Parameter Name	Description
PMTU Discovery	Click On to enable path MTU discovery on the interface, to allow the router to determine the largest MTU size supported without requiring packet fragmentation.
TCP MSS	Specify the maximum segment size (MSS) of TCP SYN packets passing through the vEdge router. By default, the MSS is dynamically adjusted based on the interface or tunnel MTU such that TCP SYN packets are never fragmented. <i>Range:</i> 552 to 1460 bytes <i>Default:</i> None
Clear Dont Fragment	Click On to clear the Don't Fragment bit in the IPv4 packet header for packets being transmitted out the interface. When the DF bit is cleared, packets larger than that interface's MTU are fragmented before being sent.
Static Ingress QoS	Select a queue number to use for incoming traffic. <i>Range:</i> 0 through 7
Autonegotiate	Click Off to turn off autonegotiation. By default, an interface runs in autonegotiation mode.



TLOC Extension	Enter the name of the physical interface on the same router that connects to the WAN transport circuit. This configuration then binds this service-side interface to the WAN transport. A second vEdge router at the same site that itself has no direct connection to the WAN (generally because the site has only a single WAN connection) and that connects to this service-side interface is then provided with a connection to the WAN.
----------------	--

To save the feature template, click Save.

## Release Information

Introduced in vManage NMS in Release 18.3.

## VPN Interface NAT Pool

Use the VPN Interface NAT Pool template for all vEdge routers.

To configure NAT pool interfaces in a VPN using vManage templates:

1. Create a VPN Interface NAT Pool template to configure Ethernet interface parameters, as described in this article.
2. Create a VPN feature template to configure parameters for a service-side VPN. See the [VPN](#) help topic.
3. Optionally, create a data policy to direct data traffic to a service-side NAT.

## Create a VPN Interface NAT Pool template and Name the Template

You can create a new VPN Interface NAT Pool template from the Service VPN section of any VPN-enabled device template.

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Service VPN tab located beneath the Description field, or scroll to the Service VPN section.

CONFIGURATION | TEMPLATES

Device Feature

Device Model vEdge 2000 ▼


Template Name

Description


Basic Information Transport & Management VPN **Service VPN** Additional Templates

6. Click the Service VPN drop-down. A VPN field opens.
7. Under Additional VPN Templates, located to the right of the screen, click VPN Interface NAT Pool.

- From the VPN Interface NAT Pool drop-down, click Create Template.



The VPN Interface NAT Pool template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN Interface NAT Pool parameters.



- In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
- Optionally, in the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure a NAT Pool Interface

To configure a NAT pool interface, you must at a minimum configure the following basic configuration and tracker parameters. Parameters marked with an asterisk are required to configure the interface.

Parameter Name	Description
Shutdown*	Click No to enable the interface.
Interface Name*	Enter a number for the NAT pool interface to use for service-side NAT. <i>Range:</i> 1 through 31
Description	Enter a description for the interface.
IPv4 Address	Enter the IPv4 address of the interface. The address length determines the number of addresses that the router can NAT at the same time. A vEdge router can NAT a maximum of 250 IP addresses.
Refresh Mode	Select how NAT mappings are refreshed: <ul style="list-style-type: none"> <li>• <b>bi-directional</b> —Keep active the NAT mappings for inbound and outbound traffic.</li> <li>• <b>outbound</b> —Keep active the NAT mappings for outbound traffic. This is the default.</li> </ul>
UDP Timeout	Enter the time when NAT translations over UDP sessions time out. <i>Range:</i> 1 through 65536 minutes <i>Default:</i> 1 minute
TCP Timeout	Enter the time when NAT translations over UDP sessions time out. <i>Range:</i> 1 through 65536 minutes <i>Default:</i> 60 minutes (1 hour)
Block ICMP	Select whether a vEdge router that is acting as a NAT device should receive inbound ICMP error messages. By default, the router blocks these error messages. Click Off to receive the ICMP error messages.
Direction	Select the direction in which the NAT interface performs address translation: <ul style="list-style-type: none"> <li>• <b>inside</b> —Translate the source IP address of packets that are coming from the service side of the vEdge router and that are destined to transport side of the router. This is the default.</li> <li>• <b>outside</b> —Translate the source IP address of packets that are coming to the vEdge router from the transport side of the vEdge router and that are destined to a service-side device.</li> </ul>
Overload	Click No to disable dynamic NAT. By default, dynamic NAT is enabled.

To save the feature template, click Save.

**CLI equivalent:**

```
vpn vpn-id
  interface natpoolnumber
    ip address prefix/length
    nat
      direction (inside | outside)
      [no] overload
      refresh (bi-directional | outbound)
      static source-ip ip-address1 translate-ip ip-address2 (inside | outside)
      tcp-timeout minutes
      udp-timeout minutes
      [no] shutdown
    tracker tracker-name
```

## Configure Port-Forwarding Rules

To create port-forwarding rules to allow requests from an external network to reach devices on the internal network, select the Port Forward tab. Then, click Add New Port Forwarding Rule, and configure the following parameters. You can create up to 128 rules.

Parameter Name	Description
Port Start Range	Enter the starting port number. This number must be less than or equal to the ending port number.
Port End Range	Enter the ending port number. To apply port forwarding to a single port, specify the same port number for the starting and ending numbers. When applying port forwarding to a range of ports, the range includes the two port numbers that you specify.
Protocol	Select the protocol to apply the port-forwarding rule to. It can be TCP or UDP. To match the same ports for both TCP and UDP traffic, configure two rules.
VPN	Private VPN in which the internal server resides. <i>Range:</i> 0 through 65535
Private IP	If the vEdge router has multiple TLOCs, click No to have the tunnel not establish a TLOC. The default is On, which establishes a control connection for the TLOC.

To save the rule, click Add.

To save the feature template, click Save.

**CLI equivalent:**

```
vpn vpn-id
  interface natpoolnumber
    nat
      port-forward port-start port-number1 port-end port-number2 proto (tcp | udp)
      private-ip-address ip address private-vpn vpn-id
```

## Configure Static NAT

To configure a static NAT address of service-side source IP addresses, select the Static NAT tab. Then click Add New Static NAT and configure the following parameters to add a static NAT mapping:

Parameter Name	Description
Source IP	Enter the private source IP address to be NATed.

Translate IP	Enter the public IP address to map the private source address to.
Static NAT Direction	<p>Select the direction in which to perform network address translation:</p> <ul style="list-style-type: none"> <li>• <b>inside</b> — Translate the IP address of packets that are coming from the service side of the vEdge router and that are destined to transport side of the router.</li> <li>• <b>outside</b> — Translate the IP address of packets that are coming to the vEdge router from the transport side of the vEdge router and that are destined to a service-side device.</li> </ul>

To save the NAT mapping, click Add.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
  interface natpoolnumber
    ip address prefix/length
    no shutdown
  nat
    direction (inside | outside)
    no overload
    static source-ip ip-address1 translate-ip ip-address2 (inside | outside)
```

## Release Information

Introduced in vManage NMS Release 16.3.

In Release 17.2.2, add support for tracker interface status.

## VPN Interface PPP

Use the VPN Interface PPP template for vEdge Cloud and vEdge router devices.

Point-to-Point Protocol (PPP) is a data link protocol used to establish a direct connection between two nodes. PPP properties are associated with a PPPoE-enabled interface on vEdge routers to connect multiple users over an Ethernet link.


To configure PPPoE on vEdge routers using vManage templates:

1. Create a VPN Interface PPP feature template to configure PPP parameters for the PPP virtual interface, as described in this article.
2. Create a VPN Interface PPP Ethernet feature template to configure a PPPoE-enabled interface. See the [VPN Interface PPP Ethernet](#) help topic.
3. Optionally, create a VPN feature template to modify the default configuration of VPN 0. See the [VPN](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Transport & Management VPN tab located directly beneath the Description field, or scroll to the Transport & Management VPN section.

- Under Additional VPN 0 Templates, located to the right of the screen, click VPN Interface PPP.



- From the VPN Interface PPP drop-down, click Create Template. The VPN Interface PPP template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN Interface PPP parameters.
- In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
- In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <a href="#">attach a Viptela device to a device template</a> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>

Global (indicated by a globe icon)	Enter a value for the parameter, and apply that value to all devices.  Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.
------------------------------------	--

## Configure a PPP Virtual Interface

To configure a PPP virtual interface, select the Basic Configuration tab and configure the following parameters. Parameters marked with an asterisk are required to configure the interface. You must also configure an authentication protocol and a tunnel interface for the PPP interface, and you must ensure that the maximum MTU for the PPP interface is 1492 bytes.

Parameter Name	Description
Shutdown*	Click No to enable the PPP virtual interface.
PPP Interface Name*	Enter the number of the PPP interface. It can be a number from 1 through 31.
Description	Enter a description for the PPP virtual interface.
Bandwidth Upstream	For transmitted traffic, set the bandwidth above which to generate notifications. <i>Range: 1 through <math>(2^{32} / 2) - 1</math> kbps</i>
Bandwidth Downstream	For received traffic, set the bandwidth above which to generate notifications. <i>Range: 1 through <math>(2^{32} / 2) - 1</math> kbps</i>
Block Non-Source IP	Click Yes to have the interface forward traffic only if the source IP address of the traffic matches the interface's IP prefix range.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn 0
  interface pppnumber
    bandwidth-downstream kbps
    bandwidth-upstream kbps
    block-non-source-ip
    ppp
    no shutdown
```

## Configure the Access Concentrator Name and Authentication Protocol

To configure the access concentrator name, select the PPP tab and configure the following parameters:

Parameter Name	Description
AC Name	Name of the access concentrator used by PPPoE to route connections to the Internet.
Authentication Protocol	Select the authentication protocol used by PPPoE: <ul style="list-style-type: none"> <li>CHAP—Enter the hostname and password provided by your Internet Service Provider (ISP). <i>hostname</i> can be up to 255 characters.</li> <li>PAP—Enter the username and password provided by your ISP. <i>username</i> can be up to 255 characters.</li> <li>PAP and CHAP—Configure both authentication protocols. Enter the login credentials for each protocol. To use the same username and password for both, click Same Credentials for PAP and CHAP.</li> </ul>

To save the feature template, click Save.

*CLI equivalent:*

## Configuration

```

vpn 0
  interface pppnumber
    ppp
      ac-name name
      authentication
        chap hostname name password password
        pap password password sent-username name

```

## Create a Tunnel Interface

On vEdge routers, you can configure up to four tunnel interfaces. This means that each vEdge router can have up to four TLOCs.

For the control plane to establish itself so that the overlay network can function, you must configure WAN transport interfaces in VPN 0.

To configure a tunnel interface for the PPP interface, select the Tunnel Interface tab and configure the following parameters:

Parameter Name	Description
Tunnel Interface	Click On to create a tunnel interface.
Color	Select a color for the TLOC.
Control Connection	If the vEdge router has multiple TLOCs, click No to have the tunnel not establish a TLOC. The default is On, which establishes a control connection for the TLOC.
Maximum Control Connections	Specify the maximum number of vSmart controllers that the WAN tunnel interface can connect to. To have the tunnel establish no control connections, set the number to 0.  <i>Range:</i> 0 through 8 <i>Default:</i> 2
vBond As STUN Server	Click On to enable Session Traversal Utilities for NAT (STUN) to allow the tunnel interface to discover its public IP address and port number when the vEdge router is located behind a NAT.
Exclude Controller Group List	Set the vSmart controllers that the tunnel interface is not allowed to connect to. <i>Range:</i> 0 through 100
vManage Connection Preference	Set the preference for using a tunnel interface to exchange control traffic with the vManage NMS. <i>Range:</i> 0 through 8 <i>Default:</i> 5
Low-Bandwidth Link	Select to characterize the tunnel interface as a low-bandwidth link.
Allow Service	Select On or Off for each service to allow or disallow the service on the interface.

To configure additional tunnel interface parameters, click Advanced Options and configure the following parameters:

Parameter Name	Description
GRE	Use GRE encapsulation on the tunnel interface. By default, GRE is disabled.  If you select both IPsec and GRE encapsulations, two TLOCs are created for the tunnel interface that have the same IP addresses and colors, but that differ by their encapsulation.
IPsec	Use IPsec encapsulation on the tunnel interface. By default, IPsec is enabled.  If you select both IPsec and GRE encapsulations, two TLOCs are created for the tunnel interface that have the same IP addresses and colors, but that differ by their encapsulation.



## Configuration

IPsec Preference	Specify a preference value for directing traffic to the tunnel. A higher value is preferred over a lower value.  <i>Range:</i> 0 through 4294967295 <i>Default:</i> 0
IPsec Weight	Enter a weight to use to balance traffic across multiple TLOCs. A higher value sends more traffic to the tunnel.  <i>Range:</i> 1 through 255 <i>Default:</i> 1
Carrier	Select the carrier name or private network identifier to associate with the tunnel.  <i>Values:</i> carrier1, carrier2, carrier3, carrier4, carrier5, carrier6, carrier7, carrier8, default <i>Default:</i> default
Bind Loopback Tunnel	Enter the name of a physical interface to bind to a loopback interface.
Last-Resort Circuit	Select to use the tunnel interface as the circuit of last resort.
NAT Refresh Interval	Enter the interval between NAT refresh packets sent on a DTLS or TLS WAN transport connection. <i>Range:</i> 1 through 60 seconds <i>Default:</i> 5 seconds
Hello Interval	Enter the interval between Hello packets sent on a DTLS or TLS WAN transport connection. <i>Range:</i> 100 through 10000 milliseconds <i>Default:</i> 1000 milliseconds (1 second)
Hello Tolerance	Enter the time to wait for a Hello packet on a DTLS or TLS WAN transport connection before declaring that transport tunnel to be down.  <i>Range:</i> 12 through 60 seconds <i>Default:</i> 12 seconds

**CLI equivalent:**

```

vpn 0
  interface interface-name
    tunnel-interface
      allow-service service-name
      bind interface-name
      carrier carrier-name
      color color
      encapsulation (gre | ipsec)
        preference number
        weight number
      hello-interval milliseconds
      hello-tolerance seconds
      last-resort-circuit
      max-control-connections number
      nat-refresh-interval seconds
      vbond-as-stun-server

```

## Configure the Interface as a NAT Device

To configure an interface to act as a NAT device, select the NAT tab and configure the following parameters:

Parameter Name	Description
----------------	-------------

NAT	Click On to have the interface act as a NAT device.
Refresh Mode	Select how NAT mappings are refreshed, either outbound or bidirectional (outbound and inbound). <i>Default</i> : Outbound
UDP Timeout	Specify when NAT translations over UDP sessions time out. <i>Range</i> : 1 through 65536 minutes <i>Default</i> : 1 minutes
TCP Timeout	Specify when NAT translations over TCP sessions time out. <i>Range</i> : 1 through 65536 minutes <i>Default</i> : 60 minutes (1 hour)
Block ICMP	Select On to block inbound ICMP error messages. By default, a vEdge router acting as a NAT device receives these error messages. <i>Default</i> : Off
Respond to Ping	Select On to have the vEdge router respond to ping requests to the NAT interface's IP address that are received from the public side of the connection.

To create a port forwarding rule, click Add New Port Forwarding Rule and configure the following parameters. You can define up to 128 port-forwarding rules to allow requests from an external network to reach devices on the internal network.

Parameter Name	Description
Port Start Range	Enter a port number to define the port or first port in the range of interest. <i>Range</i> : 0 through 65535
Port End Range	Enter the same port number to apply port forwarding to a single port, or enter the larger number to apply it to a range or ports. <i>Range</i> : 0 through 65535
Protocol	Select the protocol to which to apply the port-forwarding rule, either TCP or UDP. To match the same ports for both TCP and UDP traffic, configure two rules.
VPN	Specify the private VPN in which the internal server resides. This VPN is one of the VPN identifiers in the overlay network. <i>Range</i> : 0 through 65535
Private IP	Specify the IP address of the internal server to which to direct traffic that matches the port-forwarding rule.

To save a port forwarding rule, click Add.

To save the feature template, click Save.

#### CLI equivalent:

```
vpn vpn-id
 interface interface-name
   nat
     block-icmp-error
     port-forward port-start port-number1 port-end port-number2 proto (tcp | udp)
       private-ip-address ip-address private-vpn vpn-id
     refresh (bi-directional | outbound)
     respond-to-ping
```

## Configuration

```

tcp-timeout minutes
udp-timeout minutes

```

## Apply Access Lists

To apply a rewrite rule, access lists, and policers to a router interface, select the ACL tab and configure the following parameters:

Parameter Name	Description
Rewrite Rule	Click On, and specify the name of the rewrite rule to apply on the interface.
Ingress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being received on the interface.
Egress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being transmitted on the interface.
Ingress ACL – IPv6	Click On, and specify the name of the access list to apply to IPv6 packets being received on the interface.
Egress ACL – IPv6	Click On, and specify the name of the access list to apply to IPv6 packets being transmitted on the interface.
Ingress Policer	Click On, and specify the name of the policer to apply to packets being received on the interface.
Egress Policer	Click On, and specify the name of the policer to apply to packets being transmitted on the interface.

To save the feature template, click Save.

*CLI equivalent:*

```

vpn 0
  interface pppnumber
    access-list acl-name (in | out)
    ipv6 access-list acl-name (in | out)
    policer policer-name (in |out)
    rewrite-rule name

```

## Configure Other Interface Properties

To configure other interface properties, select the Advanced tab and configure the following properties:

Parameter Name	Description
MAC Address	Specify a MAC address to associate with the interface, in colon-separated hexadecimal notation.
IP MTU	Specify the maximum MTU size of packets on the interface. <i>Range:</i> 576 through 1804 <i>Default:</i> 1500 bytes
TCP MSS	Specify the maximum segment size (MSS) of TCP SYN packets passing through the vEdge router. By default, the MSS is dynamically adjusted based on the interface or tunnel MTU such that TCP SYN packets are never fragmented. <i>Range:</i> 552 to 1460 bytes <i>Default:</i> None
Clear Dont Fragment	Click On to clear the Don't Fragment bit in the IPv4 packet header for packets being transmitted out the interface. When the DF bit is cleared, packets larger than that interface's MTU are fragmented before being sent.
TLOC Extension	Enter the name of the physical interface on the same router that connects to the WAN transport circuit. This configuration then binds this service-side interface to the WAN transport. A second vEdge router at the same site that itself has no direct connection to the WAN (generally because the site has only a single WAN connection) and that connects to this service-side interface is then provided with a connection to the WAN.

Tracker	Enter the name of a tracker to track the status of transport interfaces that connect to the internet.
ICMP Redirect	Click Disable to disable ICMP redirect messages on the interface. By default, an interface allows ICMP redirect messages.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn vpn-id
 interface interface-name
   clear-dont-fragment
   icmp-redirect-disable
   mac-address mac-address
   mtu bytes
   tcp-mss-adjust bytes
   tloc-extension interface-name
   tracker tracker-name
```

## Release Information

Introduced in vManage NMS in Release 15.3.

In Release 16.3, add support for IPv6.

In Release 17.1, support ability to configure both CHAP and PAP authentication on a PPP interface.

In Release 17.2.2, add support for interface status tracking.

In Release 18.2, add support for disabling ICMP redirect messages.

## VPN Interface PPP Ethernet

Use the VPN Interface PPP Ethernet template for vEdge Cloud and vEdge router devices.

Point-to-Point Protocol (PPP) is a data link protocol used to establish a direct connection between two nodes. PPP properties are associated with a PPPoE-enabled interface on vEdge routers to connect multiple users over an Ethernet link.

To configure PPPoE on vEdge routers using vManage templates:


1. Create a VPN Interface PPP Ethernet feature template to configure a PPPoE-enabled interface as described in this article.
2. Create a VPN Interface PPP feature template to configure PPP parameters for the PPP virtual interface. See the [VPN Interface PPP](#) help topic
3. Optionally, create a VPN feature template to modify the default configuration of VPN 0. See the [VPN](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. Click the Transport & Management VPN tab located directly beneath the Description field, or scroll to the Transport & Management VPN section.

## Configuration

- Under Additional VPN 0 Templates, located to the right of the screen, click VPN Interface PPP.



- From the VPN Interface PPP Ethernet drop-down, click Create Template. The VPN Interface PPP Ethernet template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN Interface PPP parameters.
- In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
- In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure a Basic PPPoE-Enabled Interface

To create a PPPoE-enabled interface on a vEdge router, select the Basic Configuration tab and configure the following parameters. Parameters marked with an asterisk are required to configure the interface.

Parameter Name	Description
Shutdown*	Click No to enable the PPPoE-enabled interface.
Interface Name*	<p>Enter the name of the physical interface in VPN 0 to associate with the PPP interface.</p> <p>For IOS XE routers, you must spell out the interface names completely (for example, <b>GigabitEthernet0/0/0</b> ), and you must configure all the router's interfaces even if you are not using them so that they are configured in the shutdown state and so that all default values for them are configured.</p>
Description	Enter a description of the PPPoE-enabled interface.
IPv4 Configuration*	<p>To configure a static address, click Static and enter an IPv4 address.</p> <p>To set the interface as a DHCP client so that the interface to receive its IP address from a DHCP server, click Dynamic. You can optionally set the DHCP distance to specify the administrative distance of routes learned from a DHCP server. The default DHCP distance is 1.</p>
IPv6 Configuration*	<p>To configure a static address for an interface in VPN 0, click Static and enter an IPv6 address.</p> <p>To set the interface as a DHCP client so that the interface to receive its IP address from a DHCP server, click Dynamic. You can optionally set the DHCP distance to specify the administrative distance of routes learned from a DHCP server. The default DHCP distance is 1. You can optionally enable DHCP rapid commit, to speed up the assignment of IP addresses.</p>
DHCP Helper	Enter up to eight IP addresses for DHCP servers in the network, separated by commas, to have the interface be a DHCP helper. A DHCP helper interface forwards BOOTP (Broadcast) DHCP requests that it receives from the specified DHCP servers.
Bandwidth Upstream	For transmitted traffic, set the bandwidth above which to generate notifications. <i>Range: 1 through <math>(2^{32} / 2) - 1</math> kbps</i>
Bandwidth Downstream	For received traffic, set the bandwidth above which to generate notifications. <i>Range: 1 through <math>(2^{32} / 2) - 1</math> kbps</i>

To save the feature template, click Save.

## Configuration

**CLI equivalent:**

```

vpn 0
  interface pppnumber
    bandwidth-downstream kbps
    bandwidth-upstream kbps
    description text
    dhcp-helper ip-address
    (ip address ipv4-prefix/length | ip-dhcp-client [dhcp-distance number])
    (ipv6 address ipv6-prefix/length | ipv6 dhcp-client [dhcp-distance number] [ dhcp-rapid-commit])
    pppoe-client ppp-interface pppnumber
    [no] shutdown

```

## Apply Access Lists

To configure a shaping rate to a PPPoE-enabled interface and to apply a QoS map, a rewrite rule, access lists, and policers to the interface, select the ACL/QoS tab and configure the following parameters:

Parameter Name	Description
Shaping Rate	Configure the aggregate traffic transmission rate on the interface to be less than line rate, in kilobits per second (kbps).
QoS Map	Specify the name of the QoS map to apply to packets being transmitted out the interface.
Rewrite Rule	Click On, and specify the name of the rewrite rule to apply on the interface.
Ingress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being received on the interface.
Egress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being transmitted on the interface.
Ingress ACL – IPv6	Egress ACL – IPv6
Egress ACL – IPv6	Egress ACL – IPv6
Ingress Policer	Click On and specify the name of the policer to apply to packets being received on the interface.
Egress Policer	Click On, and specify the name of the policer to apply to packets being transmitted on the interface.

To save the feature temp

**CLI equivalent:**

```

vpn 0
  interface pppnumber
    access-list acl-list (in | out)
    policer policer-name (in |out)
    qos-map name
    rewrite-rule name
    shaping-rate name

```

## Configure Other Interface Properties

To configure other interface properties, select the Advanced tab and configure the following properties:

Parameter Name	Description
Duplex	Choose full or half to specify whether the interface runs in full-duplex or half-duplex mode. <i>Default: Full</i>

## Configuration

MAC Address	Specify a MAC address to associate with the interface, in colon-separated hexadecimal notation.
IP MTU	Specify the maximum MTU size of packets on the interface. <i>Range:</i> 576 through 1804 <i>Default:</i> 1500 bytes
PMTU Discovery	Click On to enable path MTU discovery on the interface. PMTU determines the largest MTU size that the interface supports so that packet fragmentation does not occur.
Flow Control	Select a setting for bidirectional flow control, which is a mechanism for temporarily stopping the transmission of data on the interface. <i>Values:</i> autonet, both, egress, ingress, none <i>Default:</i> autoneg
TCP MSS	Specify the maximum segment size (MSS) of TCP SYN packets passing through the vEdge router. By default, the MSS is dynamically adjusted based on the interface or tunnel MTU such that TCP SYN packets are never fragmented. <i>Range:</i> 552 to 1460 bytes <i>Default:</i> None
Speed	Specify the speed of the interface, for use when the remote end of the connection does not support autonegotiation. <i>Values:</i> 10, 100, or 1000 Mbps <i>Default:</i> Autonegotiate (10/100/1000 Mbps)
Static Ingress QoS	Specify a queue number to use for incoming traffic. <i>Range:</i> 0 through 7
ARP Timeout	Specify how long it takes for a dynamically learned ARP entry to time out. <i>Range:</i> 0 through 2678400 seconds (744 hours) <i>Default:</i> 1200 seconds (20 minutes)
Autonegotiation	Click Off to turn off autonegotiation. By default, an interface runs in autonegotiation mode.
TLOC Extension	Enter the name of a physical interface on the same router that connects to the WAN transport. This configuration then binds this service-side interface to the WAN transport. A second vEdge router at the same site that itself has no direct connection to the WAN (generally because the site has only a single WAN connection) and that connects to this service-side interface is then provided with a connection to the WAN.
Power over Ethernet (on vEdge 100m and vEdge 100wm routers)	Click On to enable PoE on the interface.
ICMP Redirect	Click Disable to disable ICMP redirect messages on the interface. By default, an interface allows ICMP redirect messages.

To save the feature template, click Save.

*CLI equivalent:*

```
vpn 0
  interface pppnumber
    arp-timeout seconds
    [no] autonegotiate
    duplex (full | half)
    flow-control control
    icmp-redirect-disable
    mac-address mac-address
    mtu bytes
    pmtu
    pppoe-client
```



## Configuration

```
ppp-interface pppnumber
speed speed
static-ingress-qos number
tcp-mss-adjust bytes
tloc-extension interface-name
```

## Release Information

Introduced in vManage NMS Release 15.3.

In Release 16.3, add support for IPv6.

In Release 18.2, add support for disabling ICMP redirect messages.

## VPN Interface SVI


Use the VPN Interface SVI template for Cisco IOS XE routers running the SD-WAN software.

You configure a switch virtual interface (SVI) to configure a VLAN interface.

To configure DSL interfaces on Cisco routers using vManage templates, create a VPN Interface SVI feature template to configure VLAN interface parameters, as described in this article.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. If you are configuring the SVI in the transport VPN (VPN 0):
  - a. Click the Transport & Management VPN tab located directly beneath the Description field, or scroll to the Transport & Management VPN section.
  - b. Under Additional VPN 0 Templates, located to the right of the screen, click VPN Interface SVI.
6. If you are configuring the SVI in a service VPN (VPNs other than VPN 0):
  - a. Click the Service VPN tab located directly beneath the Description field, or scroll to the Service VPN section.
  - b. In the Service VPN drop-down, enter the number of the service VPN.
  - c. Under Additional VPN Templates, located to the right of the screen, click VPN Interface SVI.
7. From the VPN Interface SVI drop-down, click Create Template. The VPN Interface SVI template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VLAN Interface parameters.



8. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
9. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <a href="#">attach a Viptela device to a device template</a> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure Basic Interface Functionality

To configure basic VLAN interface functionality in a VPN, select the Basic Configuration tab and configure the following parameters. Parameters marked with an asterisk are required to configure an interface.

Parameter Name	Description
Shutdown*	Click No to enable the VLAN interface.
VLAN Interface Name*	Enter the VLAN identifier of the interface. <i>Range: 1 through 1094</i>
Description	Enter a description for the interface.
IPv4 Address*	Enter the IPv4 address for the interface.
DHCP Helper*	Enter up to eight IP addresses for DHCP servers in the network, separated by commas, to have the interface be a DHCP helper. A DHCP helper interface forwards BOOTP (Broadcast) DHCP requests that it receives from the specified DHCP servers.
IP MTU	Specify the maximum MTU size of packets on the interface. <i>Range: 576 through 1804</i> <i>Default: 1500 bytes</i>

To save the feature template, click Save.

## Apply Access Lists

To apply a rewrite rule, access lists, and policers to a router interface, select the ACL tab and configure the following parameters:

Parameter Name	Description
Ingress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being received on the interface.
Egress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being transmitted on the interface.
Ingress Policer	Click On, and specify the name of the policer to apply to packets being received on the interface.
Egress Policer	Click On, and specify the name of the policer to apply to packets being transmitted on the interface.

To save the feature template, click Save.

## Configure VRRP

To have an interface run the Virtual Router Redundancy Protocol (VRRP), which allows multiple routers to share a common virtual IP address for default gateway redundancy, select the VRRP tab. Then click Add New VRRP and configure the following parameters:

Parameter Name	Description
Group ID	Enter the virtual router ID, which is a numeric identifier of the virtual router. You can configure a maximum of 24 groups. <i>Range: 1 through 255</i>
Priority	Enter the priority level of the router. The router with the highest priority is elected as primary. If two vEdge routers have the same priority, the one with the higher IP address is elected as primary. <i>Range: 1 through 254</i> <i>Default: 100</i>

Timer	Specify how often the VRRP primary sends VRRP advertisement messages. If secondary routers miss three consecutive VRRP advertisements, they elect a new primary. <i>Range:</i> 1 through 3600 seconds <i>Default:</i> 1 second
Track OMP Track Prefix List	By default, VRRP uses of the state of the service (LAN) interface on which it is running to determine which vEdge router is the primary virtual router. If a vEdge router loses all its WAN control connections, the LAN interface still indicates that it is up even though the router is functionally unable to participate in VRRP. To take WAN side connectivity into account for VRRP, configure one of the following:  Track OMP—Click On for VRRP to track the Overlay Management Protocol (OMP) session running on the WAN connection. If the primary VRRP router loses all its OMP sessions, VRRP elects a new default gateway from those that have at least one active OMP session.  Track Prefix List—Track both the OMP session and a list of remote prefixes, which is defined in a prefix list configured on the local router. If the primary VRRP router loses all its OMP sessions, VRRP failover occurs as described for the Track OMP option. In addition, if reachability to one of the prefixes in the list is lost, VRRP failover occurs immediately, without waiting for the OMP hold timer to expire, thus minimizing the amount of overlay traffic is dropped while the vEdge routers determine the VRRP primary.
IP Address	Enter the IP address of the virtual router. This address must be different from the configured interface IP addresses of both the local vEdge router and the peer running VRRP.

## Add ARP Table Entries

To configure static Address Resolution Protocol (ARP) table entries on the interface, select the ARP tab. Then click Add New ARP and configure the following parameters:

Parameter Name	Description
IP Address	Enter the IP address for the ARP entry in dotted decimal notation or as a fully qualified host name.
MAC Address	Enter the MAC address in colon-separated hexadecimal notation.

To save the ARP configuration, click Add.

To save the feature template, click Save.

## Configure Other Interface Properties

To configure other interface properties, select the Advanced tab and configure the following properties:

Parameter Name	Description
TCP MSS	Specify the maximum segment size (MSS) of TCP SYN packets passing through the vEdge router. By default, the MSS is dynamically adjusted based on the interface or tunnel MTU such that TCP SYN packets are never fragmented. <i>Range:</i> 552 to 1460 bytes <i>Default:</i> None
ARP Timeout	Specify how long it takes for a dynamically learned ARP entry to time out. <i>Range:</i> 0 through 2678400 seconds (744 hours) <i>Default:</i> 1200 (20 minutes)

To save the feature template, click Save.

## Release Information

Introduced in vManage NMS in Release 18.3.

## VPN Interface T1/E1


Use the VPN Interface T1/E1 template for Cisco IOS XE routers running the SD-WAN software.

To configure the T1/E1 interfaces in a VPN using vManage templates:

1. Create a VPN Interface T1/E1 feature template to configure T1/E1 interface parameters, as described in this article.
2. Create a T1/E1 Controller template to configure the T1 or E1 network interface module (NIM) parameters. See the [T1/E1 Controller](#) help topic.
3. Create a VPN feature template to configure VPN parameters. See the [VPN](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the type of device for which you are creating the template.
5. To create a template for VPN 0 or VPN 512:
  - a. Click the Transport & Management VPN tab located directly beneath the Description field, or scroll to the Transport & Management VPN section.
  - b. Under Additional VPN 0 Templates, located to the right of the screen, click VPN Interface.
  - c. From the VPN Interface drop-down, click Create Template. The VPN Interface T1/E1 template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN Interface Ethernet parameters.
6. To create a template for VPNs 1 through 511, and 513 through 65530:
  - a. Click the Service VPN tab located directly beneath the Description field, or scroll to the Service VPN section.
  - b. Click the Service VPN drop-down.
  - c. Under Additional VPN templates, located to the right of the screen, click VPN Interface.
  - d. From the VPN Interface drop-down, click Create Template. The VPN Interface Ethernet template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining VPN Interface Ethernet parameters.



7. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
8. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure Basic Interface Functionality

To configure basic interface functionality in a VPN, select the Basic Configuration tab and configure the following parameters. Parameters marked with an asterisk are required to configure an interface.

Parameter Name	Description
Shutdown*	Click No to enable the interface.
Interface name*	Enter a name for the interface. The name should be in the format <b>serial slot / subslot / port : channel-group</b> . You must also configure a number for the channel group in the <a href="#">T1/E1 Controller</a> feature configuration template.
Description	Enter a description for the interface.
IPv4 Address*	Enter an IPv4 address.
IPv6 Address*	Enter an IPv6 address.
Bandwidth Upstream	For transmitted traffic, set the bandwidth above which to generate notifications. <i>Range: 1 through (2<sup>32</sup> / 2) – 1 kbps</i>
Bandwidth Downstream	For received traffic, set the bandwidth above which to generate notifications. <i>Range: 1 through (2<sup>32</sup> / 2) – 1 kbps</i>
IP MTU	Specify the maximum MTU size of packets on the interface. <i>Range: 576 through 1804</i> <i>Default: 1500 bytes</i>

To save the feature template, click Save.

## Create a Tunnel Interface

You can configure up to four tunnel interfaces. This means that each vEdge router can have up to four TLOCs.

For the control plane to establish itself so that the overlay network can function, you must configure WAN transport interfaces in VPN 0.

To configure a tunnel interface, select the Interface Tunnel tab and configure the following parameters:

Parameter Name	Description
Tunnel Interface	Click On to create a tunnel interface.
Color	Select a color for the TLOC.
Control Connection	If the router has multiple TLOCs, click No to have the tunnel not establish a TLOC. The default is On, which establishes a control connection for the TLOC.
Maximum Control Connections	Specify the maximum number of vSmart controllers that the WAN tunnel interface can connect to. To have the tunnel establish no control connections, set the number to 0.  <i>Range: 0 through 8</i> <i>Default: 2</i>
vBond As Stun Server	Click On to enable Session Traversal Utilities for NAT (STUN) to allow the tunnel interface to discover its public IP address and port number when the vEdge router is located behind a NAT.
Exclude Controller Group List	Set the vSmart controllers that the tunnel interface is not allowed to connect to. <i>Range: 0 through 100</i>
vManage Connection Preference	Set the preference for using a tunnel interface to exchange control traffic with the vManage NMS. <i>Range: 0 through 8</i> <i>Default: 5</i>

Port Hop	Click On to enable port hopping, or click Off to disable it. If port hopping is enabled globally, you can disable it on an individual TLOC (tunnel interface). To control port hopping on a global level, use the <a href="#">System</a> configuration template. <i>Default:</i> Enabled (on vEdge routers); disabled (on vManage NMSs and vSmart controllers)
Low-Bandwidth Link	Select to characterize the tunnel interface as a low-bandwidth link.
Allow Service	Select On or Off for each service to allow or disallow the service on the interface.

To configure additional tunnel interface parameters, click Advanced Options:

Parameter Name	Description
Encapsulation	Select the encapsulation type to use on the tunnel interface, either IPsec or GRE. The default is IPsec.  If you select both IPsec and GRE encapsulations, two TLOCs are created for the tunnel interface that have the same IP addresses and colors, but that differ by their encapsulation.
IPsec	By default, IPsec is enabled on the tunnel interface. To disable IPsec, click Off.
IPsec Preference	Specify a preference value for directing traffic to the tunnel. A higher value is preferred over a lower value. <i>Range:</i> 0 through 4294967295 <i>Default:</i> 0
IPsec Weigh	Enter a weight to use to balance traffic across multiple TLOCs. A higher value sends more traffic to the tunnel. <i>Range:</i> 1 through 255 <i>Default:</i> 1
Carrier	Select the carrier name or private network identifier to associate with the tunnel.  <i>Values:</i> carrier1, carrier2, carrier3, carrier4, carrier5, carrier6, carrier7, carrier8, default <i>Default:</i> default
Bind Loopback Tunnel	Enter the name of a physical interface to bind to a loopback interface.
Last-Resort Circuit	Select to use the tunnel interface as the circuit of last resort.
NAT Refresh Interval	Enter the interval between NAT refresh packets sent on a DTLS or TLS WAN transport connection. <i>Range:</i> 1 through 60 seconds <i>Default:</i> 5 seconds
Hello Interval	Enter the interval between Hello packets sent on a DTLS or TLS WAN transport connection. <i>Range:</i> 100 through 10000 milliseconds <i>Default:</i> 1000 milliseconds (1 second)
Hello Tolerance	Enter the time to wait for a Hello packet on a DTLS or TLS WAN transport connection before declaring that transport tunnel to be down.  <i>Range:</i> 12 through 60 seconds <i>Default:</i> 12 seconds

To save the feature template, click Save.

## Apply Access Lists and QoS Parameters (on vEdge Routers)

To configure a shaping rate to a router interface and to apply a QoS map, a rewrite rule, access lists, and policers to a router interface, select the ACLtab and configure the following parameters:



## Configuration

Parameter Name	Description
Shaping Rate	Configure the aggregate traffic transmission rate on the interface to be less than line rate, in kilobits per second (kbps).
QoS Map	Specify the name of the QoS map to apply to packets being transmitted out the interface.
Rewrite Rule	Click On, and specify the name of the rewrite rule to apply on the interface.
Ingress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being received on the interface.
Egress ACL – IPv4	Click On, and specify the name of the access list to apply to IPv4 packets being transmitted on the interface.
Ingress ACL – IPv6	Click On, and specify the name of the access list to apply to IPv6 packets being received on the interface.
Egress ACL – IPv6	Click On, and specify the name of the access list to apply to IPv6 packets being transmitted on the interface.
Ingress Policer	Click On, and specify the name of the policer to apply to packets received on the interface.
Egress Policer	Click On, and specify the name of the policer to apply to packets being transmitted on the interface.

To save the feature template, click Save.

## Configure Other Interface Properties

To configure other interface properties, select the Advanced tab and configure the following parameters:

Parameter Name	Description
PMTU Discovery	Click On to enable path MTU discovery on the interface. PMTU determines the largest MTU size that the interface supports so that packet fragmentation does not occur.
TCP MSS	Specify the maximum segment size (MSS) of TCP SYN packets passing through the vEdge router. By default, the MSS is dynamically adjusted based on the interface or tunnel MTU such that TCP SYN packets are never fragmented. <i>Range:</i> 552 to 1460 bytes <i>Default:</i> None
Clear-Don't-Fragment	Click On to clear the Don't Fragment (DF) bit in the IPv4 packet header for packets being transmitted out the interface. When the DF bit is cleared, packets larger than that interface's MTU are fragmented before being sent.
Static Ingress QoS	Specify a queue number to use for incoming traffic. <i>Range:</i> 0 through 7
Autonegotiation	Click Off to turn off autonegotiation. By default, an interface runs in autonegotiation mode.
TLOC Extension	Enter the name of a physical interface on the same router that connects to the WAN transport. This configuration then binds this service-side interface to the WAN transport. A second vEdge router at the same site that itself has no direct connection to the WAN (generally because the site has only a single WAN connection) and that connects to this service-side interface is then provided with a connection to the WAN.

## Release Information

Introduced in vManage NMS Release 18.2.

## WiFi Radio


Use the WiFi Radio template for all vEdge router devices that support wireless LANs (WLANs), including the vEdge 100wm router.

To configure WLAN radio parameters using vManage templates:

1. Create a WiFi Radio template to configure WLAN radio parameters, as described in this article.
2. Create a Wifi SSID template to configure an SSID and related parameters. See the [WiFi SSID](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select the vEdge router model that supports wireless LANs (WLANs).
5. Click the WLAN tab located directly beneath the Description field, or scroll to the WLAN section.
6. From the WiFi Radio drop-down, click Create Template. The WiFi Radio template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining WiFi Radio parameters.



7. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.
8. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## Configure the WLAN Radio Frequency

To configure the WLAN radio frequency, in the Basic Configuration tab, configure the following parameters. Parameters marked with an asterisk are required to configure the radio.

Parameter Name	Description
Select Radio*	Select the radio band. It can be 2.4 GHz or 5 GHz.
Country*	Select the country where the router is installed.
Channel Bandwidth	Select the IEEE 802.11n and 802.11ac channel bandwidth. For a 5-GHz radio band, the default value is 80 MHz, and for 2.4 GHz, the default is 20 MHz.
Channel	Select the radio channel. The default is "auto", which automatically selects the best channel. For 5-GHz radio bands, you can configure dynamic frequency selection (DFS) channels.
Guard Interval	Select the guard interval. For a 5-GHz radio band, the default value is the short guard interval (SGI) of 400 ns, and for 2.4 GHz, the default is 800 ns.

To save the feature template, click Save.

*CLI equivalent:*

```
wlan frequency
  channel channel
  channel-bandwidth megahertz
  country country
  guard-interval nanoseconds
```

## Release Information

Introduced in vManage NMS Release 16.3.

## WiFi SSID

You can use the WiFi SSID template for all vEdge router devices that support wireless LANs (WLANs), including vEdge 100vm routers

To configure SSIDs on the WLAN radio using vManage templates:

## Configuration

1. Create a WiFi SSID template to configure the VAP interfaces to use as SSIDs, as described in this article.
2. Create a WiFi Radio template to configure WLAN radio parameters. See the Configuration ► Templates ► [WiFi Radio](#) help topic.
3. Create a Bridge template to assign the VAP interface to a bridging domain. See the Configuration ► Templates ► [Bridge](#) help topic.
4. Create a device template that incorporates the WiFi Radio feature template and the Wifi SSID feature template. See the Configuration ► [Templates](#) help topic.

## Navigate to the Template Screen and Name the Template

1. In vManage NMS, select the Configuration ► Templates screen.
2. In the Device tab, click Create Template.
3. From the Create Template drop-down, select From Feature Template.
4. From the Device Model drop-down, select a vEdge router model that supports wireless LANs (WLANs).
5. Click the WLAN tab located directly beneath the Description field, or scroll to the WLAN section.
6. Under Additional WiFi Radio Templates, located to the right of the screen, click WiFi SSID.

The screenshot shows the Cisco vManage interface for configuring a WiFi SSID template. The left sidebar contains navigation options: Dashboard, Monitor, Configuration (selected), Devices, Certificates, Templates, Policies, Security, CloudExpress, Cloud onRamp, Tools, Maintenance, Administration, and vAnalytics. The main content area is titled 'CONFIGURATION | TEMPLATES' and has tabs for 'Device' and 'Feature'. Under the 'Feature' tab, there is a breadcrumb 'Feature Template > Add Template > WiFi SSID'. The 'Device Type' is set to 'vEdge 100 WM'. Below this are input fields for 'Template Name' and 'Description'. A 'BASIC CONFIGURATION' section contains several fields: 'Interface Name' (a dropdown menu currently showing '- Choose -'), 'Shutdown' (radio buttons for 'Yes' and 'No', with 'Yes' selected), 'Description' (a text input field), 'SSID' (a text input field), 'Maximum Clients' (a dropdown menu set to '20'), and 'Data Security' (a dropdown menu set to 'None'). At the bottom right of the form are 'Save' and 'Cancel' buttons.

7. From the WiFi SSID drop-down, click Create Template. The WiFi SSID template form is displayed. The top of the form contains fields for naming the template, and the bottom contains fields for defining WiFi SSID parameters.
8. In the Template Name field, enter a name for the template. The name can be up to 128 characters and can contain only alphanumeric characters.

## Configuration

9. In the Template Description field, enter a description of the template. The description can be up to 2048 characters and can contain only alphanumeric characters.

When you first open a feature template, for each parameter that has a default value, the scope is set to Default (indicated by a check mark), and the default setting or value is shown. To change the default or to enter a value, click the scope drop-down to the left of the parameter field and select one of the following:

Parameter Scope	Scope Description
Device Specific (indicated by a host icon)	<p>Use a device-specific value for the parameter. For device-specific parameters, you cannot enter a value in the feature template. You enter the value when you <b>attach a Viptela device to a device template</b> .</p> <p>When you click Device Specific, the Enter Key box opens. This box displays a key, which is a unique string that identifies the parameter in a CSV file that you create. This file is an Excel spreadsheet that contains one column for each key. The header row contains the key names (one key per column), and each row after that corresponds to a device and defines the values of the keys for that device. You upload the CSV file when you attach a Viptela device to a device template. For more information, see <a href="#">Create a Template Variables Spreadsheet</a> .</p> <p>To change the default key, type a new string and move the cursor out of the Enter Key box.</p> <p>Examples of device-specific parameters are system IP address, hostname, GPS location, and site ID.</p>
Global (indicated by a globe icon)	<p>Enter a value for the parameter, and apply that value to all devices.</p> <p>Examples of parameters that you might apply globally to a group of devices are DNS server, syslog server, and interface MTUs.</p>

## WLAN SSID Configuration

To configure SSIDs on a vEdge router, configuring the following parameters in the Basic Configuration tab. Parameters marked with an asterisk are required to configure the SSIDs.

Parameter Name	Description
Interface Name*	Select the VAP interface name.
Shutdown*	Click No to enable the interface.
Description (optional)	Enter a description for the interface.
SSID*	<p>Enter the name of the SSID. It can be a string from 4 through 32 characters. The SSID must be unique.</p> <p>You can configure up to four SSIDs.</p> <p>Each SSID is called a virtual access point (VAP) interface. To a client, each VAP interfaces appears as a different access point (AP) with its own SSID. To provide access to different networks, assign each VAP to a different VLAN.</p>
Maximum Clients	<p>Enter the maximum number of clients allowed to connect to the WLAN.</p> <p><i>Range:</i> 1 through 50</p> <p><i>Default:</i> 25</p>
Data Security	<p>Select the security type to enable user authentication or enterprise WPA security.</p> <p>For user authentication, select from WPA Personal, WPA/WPA2 Personal, or WPA2 Personal, and then enter a clear text or an AES-encrypted key.</p> <p>For enterprise security, select from WPA Enterprise, WPA/WPA2 Enterprise, or WPA2 Enterprise, and then enter a RADIUS server tag.</p>

RADIUS Server	If you select one of the enterprise security methods based on using a RADIUS authentication server, enter the RADIUS server tag.
WPA Personal Key	If you select one of the personal security methods based on preshared keys, enter either a clear text or an AES-encrypted password.
Management Security	If you select one of the WPA2 security methods, select the encryption of management frames to be none, optional, or required.

To save the feature template, click Save.

*CLI equivalent:*

```
wlan frequency
  interface vapnumber
    data-security security
    description text
    mgmt-security security
    radius-servers tag
    no shutdown
    ssid ssid
    wpa-personal-key password
```

## Release Information

Introduced in vManage NMS Release 16.3.

## Dashboard


### Dashboard

Use the dashboard screen to monitor, at a glance, the overall health of the Viptela overlay network.

### Top Bar

The top bar is located at the top of every vManage screen and includes the following screen elements:

- Menu icon—Click the icon to expand or collapse the vManage menu. The vManage menu is closed by default.
- vManage application server logo. To change the logo, see [How to Load a Custom Logo onto the vManage Web Application Server](#).
- Cloud onRamp icon—Enables Cloud onRamp service to optimize access to cloud applications. When Cloud onRamp service is enabled, the icon turns blue.
- Tasks icon—Click on the icon to see a list of all active and completed tasks started from the vManage NMS. While the task is in progress, the Tasks tab displays a counter on the top. When the task is completed, the count disappears and Completed Tasks count is incremented. To view details about any task, click the task to display its Status screen.
- Alarm bell icon—Displays the total count of all active alarms. Click on the icon to see a list of all active and cleared alarms. To view details about any alarm, click the alarm to display its Alarms Details screen.
- Help—Links to product help, software version information about the vManage NMS software, and current time and timezone on the vManage server.
- Hostname—Hostname of the vManage NMS that you are logged into.
- User profile drop-down—Click to sign out or edit user-related options in your profile.



## Device Pane

The Device pane, which runs across the top of the Dashboard screen, displays all control connections from the vManage NMS to the vSmart controllers, vEdge routers, and vBond orchestrators in the overlay network. It also displays the status of the vManage NMSs in the network.

For each device, the Device pane shows:

- Total number of connections.
- Number of up connections.
- Number of down connections.

Click the number or the Up or Down arrow to display a table with detailed information for each connection. The Dashboard page automatically refreshes when the status of the members of a vManage cluster changes.

Click the More Actions icon to the right of each table row to access the Device Dashboard or Real Time view in the Monitor ► Network screen or to access the Tools ► SSH Terminal screen.

## Reboot Pane

The Reboot pane displays the total number of reboots in the last 24 hours for all devices in the network, including soft and cold reboots and reboots that occurred as a result of power-cycling a device. Click the Reboot pane to open the Reboot popup window which lists, for each reboot, the system IP and hostname of the device that rebooted, the time the reboot occurred, and the reason for the reboot. If the same device reboots more than each, each reboot option is reported separately.



## Dashboard

In the Reboot popup window, click the Crashes tab to list, for all device crashes, the system IP and hostname of the device on which the crash occurred, the crash index, and the core time and filename.

## Certificates Pane

The Certificates pane displays the state of all certificates on all controller devices, and it shows a count of all expired or invalidated certificates. Click the Certificates pane to open the Certificate Details popup window, which displays the hostname and system IP of the device on which the certificate is installed, the certificate serial number, and its expiration date and status.

## Control Status Pane

The Control Status pane displays whether vSmart and vEdge devices are connected to the required number of vSmart controllers. Each vSmart controller must connect to all other vSmart controllers in the network. Each vEdge router must connect to the configured maximum number of vSmart controllers.

The Control Status pane shows three counts:

- Control Up—Total number of devices with the required number of operational control plane connections to a vSmart controller.
- Partial—Total number of devices with some, but not all, operational control plane connections to vSmart controllers.
- Control Down—Total number of devices with no control plane connection to a vSmart controller.

Click any row to display a table with device details. Click the More Actions icon to the right of each table row to access the Device Dashboard or Device Details view in the Monitor ► Network screen.

## Site Health View Pane

The Site Health View pane displays the state of a site's data connections. When a site has multiple vEdge routers, this pane displays the state for the entire site, not for individual devices. The Site Health View pane displays three states:

- Full WAN Connectivity—Total number of sites where all BFD sessions on all vEdge routers are in the up state.
- Partial WAN Connectivity—Total number of sites where a TLOC or a tunnel is in the down state. These sites still have limited data plane connectivity.
- No WAN Connectivity—Total number of sites where all BFD sessions on all vEdge routers are in the down state. These sites have no data plane connectivity.

Click a row to display a popup window with detailed information on each site, node, or tunnel. Click the More Actions icon to the right of each table row to access the Device Dashboard or Real Time view in the Monitor ► Network screen or the Tools ► SSH Terminal screen.

## Transport Interface Distribution

The Transport Interface Distribution pane displays interface usage in the last 24 hours for all vEdge interfaces in VPN 0. This includes all TLOC interfaces. Click a row to see details of interface usage.

## vEdge Inventory Pane

The vEdge Inventory pane provides four counts:

- Total—Total number of vEdge routers whose authorized serial number has been uploaded on the vManage server. The serial number is uploaded in the Configuration ► Devices screen.

## Dashboard

- **Authorized**—Total number of authorized vEdge routers in the overlay network. These are routers marked as Valid in the Configuration ► Certificates ► vEdge List screen.
- **Deployed**—Total number of deployed vEdge routers. These are routers marked as Valid that are now operational in the network.
- **Staging**—Total number of vEdge routers in staging state. These are routers you configure at a staging site before shipping them to the actual branch and making them a part of the overlay network. These routers do not take part in any routing decisions nor do they affect network monitoring through the vManage NMS.

Click any row to display a table with the hostname, system IP, site ID, and other details of each router.

## vEdge Health Pane

The vEdge Health pane displays an aggregated view for each router state and a count of how many vEdge routers are in that state, thereby describing the health of the hardware nodes. The three states are:

- **Normal**—Number of routers with memory, hardware, and CPU in normal state. Using less than 70% of total memory or total CPU is classified as normal.
- **Warning**—Number of routers with memory, hardware, or CPU in warning state. Using between 70% and 90% of total memory or total CPU is classified as a warning.
- **Error**—Number of routers with memory, hardware, or CPU in error state. Using more than 90% of total memory or total CPU is classified as an error.

Click the number or the state to display a table with the last 12 or 24 hours of memory usage, CPU utilization, and hardware-related alarms, including temperature, power supply, and PIM modules. Click the More Actions icon to the right of each table row to access the Device Dashboard or Device Details view in the Monitor ► Network screen or the Tools ► SSH Terminal screen.

## Transport Health Pane

The Transport Health pane displays the aggregated average loss, latency, and jitter for all links and all combinations of colors (for example, all LTE-to-LTE links, all LTE-to-3G links).

From the Type drop-down, select loss, latency, or jitter.

Click the Filter icon to select a time period for which to display data.

Click the Expand icon to open the Transport Health pop-up window. This full-screen window displays a more detailed view of the same information. To display the information in tabular format, click the Details tab. You can change the displayed type and time period as described above.

## Top Applications Pane

The Top Applications pane displays DPI flow information for traffic transiting vEdge routers in the overlay network.

Click the Filter icon to select a time period for which to display data. From the VPN drop-down list, select a VPN to display DPI information for all flows in that VPN.

Click the Expand icon to open the Top Applications pop-up window. This full-screen window displays a more detailed view of the same information. You can change the VPN and time period as described above.

## Application-Aware Routing Pane

The Application-Aware Routing pane displays the 10 worst tunnels based on criteria you specify from the Type drop-down list, including loss, latency, and jitter. So, if you choose loss, this pane shows the ten tunnels with the greatest average loss over the last 24 hours.

Click any row to display a graphical representation of the data. Select a time period for which to display data or click Custom to display a drop-down for specifying a custom time period.

Click the Expand icon to open the Application-Aware Routing pop-up window. This full-screen window displays the 25 worst tunnels based on criteria you specify from the Type drop-down list, including loss, latency, and jitter.

## Web Server Certificate Expiration Date Notification

When you establish a secure connection between your web browser and the vManage server using authentication certificates, you configure the time period for which the certification is valid, in the Administration ► Settings screen. At the end of this time period, the certificate expires. The Web Server Certificate bar shows the expiration date and time.

Starting 60 days before the certificate expires, the vManage Dashboard displays a notification indicating that the certificate is about to expire. This notification is then redisplayed 30, 15, and 7 days before the expiration date, and then daily.

## Maintenance Window Alert Notification

If an upcoming maintenance window is configured on the vManage server, in the Administration ► Settings screen, the vManage Dashboard displays a maintenance window alert notification two days before the start of the window.

## Multitenant Dashboard


Use the multitenant dashboard screen to monitor, at a glance, the overall health of all tenants being managed by a single vManage NMS server.

## Top Bar

The top bar is located at the top of every vManage multitenant screen and includes the following screen elements:

- Menu icon—Click the icon to expand or collapse the vManage menu. The vManage menu is closed by default.
- vManage application server logo. To change the logo, see [How to Load a Custom Logo onto the vManage Web Application Server](#).
- Provider Name—Displays the service provider name. Click the Select Tenant drop-down to display information for a single tenant.
- Alarm bell icon—Displays the total count of all active alarms. Click on the icon to see a list of all active and cleared alarms. To view details about any alarm, click the alarm to display its Alarms Details screen.
- Tasks icon—Click on the icon to see a list of all active and completed tasks started from the vManage NMS. While the task is in progress, the Tasks tab displays a counter on the top. When the task is completed, the count disappears and Completed Tasks count is incremented. To view details about any task, click the task to display its Status screen.
- Help—Links to product help, software version information about the vManage NMS software, and current time and timezone on the vManage server.
- Hostname—Hostname of the vManage NMS that you are logged into.
- User profile drop-down—Click to sign out or edit user-related options in your profile.

## Dashboard



## Provider Dashboard

If you click Provider Name in the Top Bar, the Multitenant Dashboard shows the following components:

- **Device Pane**—Runs across the top of the Multitenant Dashboard screen. The Device pane displays the total number control connections from the vManage NMS to the vBond orchestrators and vManage NMSs in the overlay networks of all the tenants, and the number of up and down connections. Click the number or the Up or Down arrow to display a table with detailed information for each connection. This pane also displays the number of warning messages and the number of invalid certificates.
- **Tenants Pane**—Displays the total number of tenants and a summary of the control status, site health, vEdge router health, and vSmart controller status for all tenants.
- **Search box**—Includes the Search Options drop-down, for a Contains or Match string.
- **Table of tenants in the overlay network**—To re-arrange the columns, drag the column title to the desired position.

## Tenant Dashboard

If you select a tenant from the Provider Name drop-down in the Top Bar, the Multitenant Dashboard shows the components described below.

### Device Pane

The Device pane, which runs across the top of the Dashboard screen, displays all control connections from the vManage NMS to the vSmart controllers and vEdge routers in the tenant's overlay network. It also displays the status of the vManage NMSs in the network.

For each device, the Device pane shows:

- Total number of connections.
- Number of up connections.

## Dashboard

- Number of down connections.

Click the number or the Up or Down arrow to display a table with detailed information for each connection. Click the More Actions icon to the right of each table row to access the Device Dashboard or Real Time view in the Monitor ► Network screen or to access the Tools ► SSH Terminal screen.

## Reboot Pane

The Reboot pane displays the total number of reboots in the last 24 hours for all devices in the network, including soft and cold reboots and reboots that occurred as a result of power-cycling a device. Click the Reboot pane to open the Reboot popup window which lists, for each reboot, the system IP and hostname of the device that rebooted, the time the reboot occurred, and the reason for the reboot. If the same device reboots more than each, each reboot option is reported separately.

In the Reboot popup window, click the Crashes tab to list, for all device crashes, the system IP and hostname of the device on which the crash occurred, the crash index, and the core time and filename.

## Control Status Pane

The Control Status pane displays whether vSmart and vEdge devices are connected to the required number of vSmart controllers. Each vSmart controller must connect to all other vSmart controllers in the network. Each vEdge router must connect to the configured maximum number of vSmart controllers.

The Control Status pane shows three counts:

- Control Up—Total number of devices with the required number of operational control plane connections to a vSmart controller.
- Partial—Total number of devices with some, but not all, operational control plane connections to vSmart controllers.
- Control Down—Total number of devices with no control plane connection to a vSmart controller.

Click any row to display a table with device details. Click the More Actions icon to the right of each table row to access the Device Dashboard or Device Details view in the Monitor ► Network screen.

## Site Health View Pane

The Site Health View pane displays the state of a site's data connections. When a site has multiple vEdge routers, this pane displays the state for the entire site, not for individual devices. The Site Health View pane displays three states:

- Full Connectivity—Total number of sites where all BFD sessions on all vEdge routers are in the up state.
- Partial Connectivity—Total number of sites where a TLOC or a tunnel is in the down state. These sites still have limited data plane connectivity.
- No Connectivity—Total number of sites where all BFD sessions on all vEdge routers are in the down state. These sites have no data plane connectivity.

Click a row to display a popup window with detailed information on each site, node, or tunnel. Click the More Actions icon to the right of each table row to access the Device Dashboard or Real Time view in the Monitor ► Network screen or the Tools ► SSH Terminal screen.

## Transport Interface Distribution Pane

The Transport Interface Distribution pane displays interface usage in the last 24 hours for all vEdge interfaces in VPN 0. This includes all TLOC interfaces. Click a row to see details of interface usage.

## vEdge Inventory Pane

The vEdge Inventory pane provides four counts:

- **Total**—Total number of vEdge routers whose authorized serial number has been uploaded on the vManage server. The serial number is uploaded in the Configuration ► Devices screen.
- **Authorized**—Total number of authorized vEdge routers in the overlay network. These are routers marked as Valid in the Configuration ► Certificates ► vEdge List screen.
- **Deployed**—Total number of deployed vEdge routers. These are routers marked as Valid that are now operational in the network.
- **Staging**—Total number of vEdge routers in staging state. These are routers you configure at a staging site before shipping them to the actual branch and making them a part of the overlay network. These routers do not take part in any routing decisions nor do they affect network monitoring through the vManage NMS.

Click any row to display a table with the hostname, system IP, site ID, and other details of each router.

## vEdge Health Pane

The vEdge Health pane displays an aggregated view for each router state and a count of how many vEdge routers are in that state, thereby describing the health of the hardware nodes. The three states are:

- **Normal**—Number of routers with memory, hardware, and CPU in normal state. Using less than 70% of total memory or total CPU is classified as normal.
- **Warning**—Number of routers with memory, hardware, or CPU in warning state. Using between 70% and 90% of total memory or total CPU is classified as a warning.
- **Error**—Number of routers with memory, hardware, or CPU in error state. Using more than 90% of total memory or total CPU is classified as an error.

Click the number or the state to display a table with the last 12 or 24 hours of memory usage, CPU utilization, and hardware-related alarms, including temperature, power supply, and PIM modules. Click the More Actions icon to the right of each table row to access the Device Dashboard or Device Details view in the Monitor ► Network screen or the Tools ► SSH Terminal screen.

## Transport Health Pane

The Transport Health pane displays the aggregated average loss, latency, and jitter for all links and all combinations of colors (for example, all LTE-to-LTE links, all LTE-to-3G links).

From the Type drop-down, select loss, latency, or jitter.

Click the Filter icon to select a time period for which to display data.

Click the Expand icon to open the Transport Health pop-up window. This full-screen window displays a more detailed view of the same information. To display the information in tabular format, click the Details tab. You can change the displayed type and time period as described above.

## Top Applications Pane

The Top Applications pane displays DPI flow information for traffic transiting vEdge routers in the overlay network.

Click the Filter icon to select a time period for which to display data. From the VPN drop-down list, select a VPN to display DPI information for all flows in that VPN.

Click the Expand icon to open the Top Applications pop-up window. This full-screen window displays a more detailed view of the same information. You can change the VPN and time period as described above.

## Application-Aware Routing Pane

The Application-Aware Routing pane displays the 10 worst tunnels based on criteria you specify from the Type drop-down list, including loss, latency, and jitter. So, if you choose loss, this pane shows the ten tunnels with the greatest average loss over the last 24 hours.

Click any row to display a graphical representation of the data. Select a time period for which to display data or click Custom to display a drop-down for specifying a custom time period.

Click the Expand icon to open the Application-Aware Routing pop-up window. This full-screen window displays the 25 worst tunnels based on criteria you specify from the Type drop-down list, including loss, latency, and jitter.

## Maintenance

### Device Reboot

Use the Device Reboot screen to reboot one or more Viptela devices.

### Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Device Reboot.
- vEdge tab bar—Includes the Controller and vManage tabs.
- Reboot button—Select a device from the table to activate the button and reboot the device. The Rows Selected box displays the number of rows selected in the table.
- Device Group drop-down—List of all configured device groups in the network.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Refresh icon—Click to refresh data in the device table with the most current data.
- Show Table Fields icon—Click to display or hide columns from the device table. By default, all columns are displayed.
- Table of devices in the overlay network—To re-arrange the columns, drag the column title to the desired position.

The screenshot displays the 'MAINTENANCE | DEVICE REBOOT' screen in Cisco vManage. The interface includes a top navigation bar with the Cisco vManage logo and user profile 'admin'. A left sidebar provides navigation to various sections: Dashboard, Monitor, Configuration, Tools, Maintenance (highlighted), Software Repository, Software Upgrade, Device Reboot, Administration, and vAnalytics. The main content area shows the 'WAN Edge' tab selected, with a 'Reboot' button and a '0 Rows Selected' indicator. Below this is a search bar for 'Device Group' and a 'Search Options' dropdown. The central table lists devices with the following columns: Hostname, System IP, Chassis Number, Device Model, Reachability, Site ID, and Up Since. The table contains 8 rows of data, with some devices marked as 'unreachable'.

	Hostname	System IP	Chassis Number	Device Model	Reachability	Site ID	Up Since
<input type="checkbox"/>	C1111-8P	172.16.255.138	C1111-8P-FOC215124MH	vEdge 1000	unreachable	2001	04 Jun 2018 1:05:00 PM PDT
<input type="checkbox"/>	CSR-cEdge1	172.16.255.130	CSR-97a0fe05-a03e-4a1c-afb3-...	CSR1000v	reachable	1600	13 Apr 2018 12:56:00 PM PDT
<input type="checkbox"/>	CSR-cEdge2	172.16.255.134	CSR-e109d8c2-7541-40d3-b3f-...	CSR1000v	reachable	1900	12 Apr 2018 3:40:00 PM PDT
<input type="checkbox"/>	ISR4221	172.16.255.139	ISR4221/K9-FOC22034WR7	ISR4221	reachable	2000	05 Jun 2018 11:19:00 AM PDT
<input type="checkbox"/>	ISR4331-S...	172.16.255.129	ISR4331-FDQ2106254L	ISR4331	unreachable	1800	25 Apr 2018 11:20:00 AM PDT
<input type="checkbox"/>	ym1	172.16.255.11	537fcec5-00f8-4062-a894-9db...	vEdge Cloud	reachable	100	23 Apr 2018 3:02:00 PM PDT
<input type="checkbox"/>	ym11	172.16.255.21	f3967a34-d454-49cd-8494-05c...	vEdge Cloud	reachable	100	04 Jun 2018 1:07:00 PM PDT
<input type="checkbox"/>	ym4	172.16.255.14	3de2abff-0261-4718-b4d2-023...	vEdge Cloud	reachable	400	23 Apr 2018 3:02:00 PM PDT



## Reboot a Device

To reboot one or more Viptela device in the overlay network:

1. In the title bar, click vEdge, Controller, or vManage.
2. Select one or more devices.
3. Click the Reboot button.

## View Active Devices

To view a list of devices on which the reboot operation has been performed:

1. Click the Tasks icon located in the vManage toolbar. vManage NMS displays a list of all running tasks along with the total number of successes and failures.
2. Click a row to see details of a task. vManage NMS opens a status window displaying the status of the task and details of the device on which the task was performed.

## Software Repository

Use the Software Repository screen to download software images to the vManage software repository.

## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Software Repository.
- Add New Software drop-down (on Repository screen)—Upload new software images to the vManage or remote server.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Refresh icon—Click to refresh data in the device table with the most current data.
- Show Table Fields icon—Click to display or hide columns from the device table. By default, all columns are displayed.
- Software repository table—List the images in the vManage software repository.

Software Version	Controller Version	Software Location	Version Type Name	Available Files
16.8.55	18.1.x	vmanage	software	csr1000v-sdwank9.16.8.55.SSA.bin
16.10.565	18.4.x	vmanage	software	isr4200-sdwank9.16.10.565.SSA.bin

## View Software Images

When you open the Software Repository screen, the images in the repository are displayed in the table. To filter the list, search or type a string in the Search box.

The Software Version column lists the version of the software image, and the Controller Version column lists the version of controller software that is equivalent to the software version. The controller version is the minimum supported vManage controller version. The software image can operate with the listed controller version or with a higher controller version. In the following example:

Software Version	Controller Version	Software Location	Version Type Name	Available Files	Updated On
16.8.55	18.1.x	vmanage	software	csr1000v-edwank9.16.8.55.SSA.bin	20 Jun 2018 10:48:35 AM PDT

The software version is 16.8.55, and the controller version is 18.1.x. Reading these two columns together tells you that software version 16.8.55 is compatible with vManage controller software versions 18.1.x and later. This means that devices running version 16.8.55 can operate with vManage servers running Releases 18.1, 18.2, and 18.3, and with later software releases, and they cannot operate with vManage servers running Release 17.2 or Release 17.1.

The Software Location column indicates where the software images are stored, either in the repository on the vManage server or in a repository in a remote location.

The Available Files column lists the names of the software image files.

The Update On column shows when the software image was added to the repository.

In the More Actions column, you can delete a software image from the repository.

## Add Software Images to the Repository

Before you can upgrade the software on a vEdge router, vSmart controller, or vManage NMS to a new software version, you need to add the software image to the vManage software repository. The repository allows you to store software images on the local vManage server and on a remote file server.

The vManage software repository allows you to store images in three ways:

- On the local vManage server, to be downloaded over a control plane connection—Here, the software images are stored on the local vManage server, and they are downloaded to the Viptela devices over a control plane connection. The receiving device generally throttles the amount of data traffic it can receive over a control plane connection, so for large files, the vManage server might not be able to monitor the software installation on the device even though it is proceeding correctly.
- On the local vManage server, to be downloaded over an out-of-band connection—Here, the software images are stored on the local vManage server, and they are downloaded to the Viptela devices over an out-of-band management connection. For this method to work, you specify the IP address of the out-of-band management interface when you copy the images to the software repository. This method is recommended when the software image files are large, because it bypasses any throttling that the device might perform and so the vManage server is able to monitor the software installation.
- On a remote server—Here, the software images remain on a remote file server that is reachable through an FTP or HTTP URL. As part of the software upgrade process, the vManage server sends this URL to the Viptela device, which then establishes a connection to the file server over which to download the software images.

To add software images to the vManage software repository:

1. Click Add New Software.
2. Select the location to store the software image:
  - a. To store the software image on the local vManage server and have it be downloaded to Viptela devices over a control plane connection, select vManage. The Upload Software to vManage dialog box opens.
    - i. Drag and drop the software image file to the dialog box, or click Browse to select the software image from a directory on the local vManage server.
    - ii. Click Upload to add the image to the software repository. The Software Repository tables displays the added software image, and it is available for installing on the devices.
  - b. To store the software image on a remote server, select Remote Server. The Location of Software on Remote Server dialog box opens.
    - i. In the Version box, enter the version number of the software image.
    - ii. In the URL box, enter the FTP or HTTP URL of the software image.
    - iii. Click Add to add the image to the software repository. The Software Repository tables displays the added software image, and it is available for installing on the devices.
  - c. To store the image on a remote vManage server and have it be downloaded to Viptela devices over an out-of-band management connection, select Remote Server - vManage. The Upload Software to Remote Server - vManage dialog box opens.
    - i. In the vManage Hostname box, enter the IP address of an interface on the vManage server that is in a management VPN (typically, VPN 512).
    - ii. Drag and drop the software image file to the dialog box, or click Browse to select the software image from a directory on the local vManage server.
    - iii. Click Upload to add the image to the software repository. The Software Repository tables displays the added software image, and it is available for installing on the devices.

## Delete a Software Image from the Repository

To delete a software image from the vManage software repository:

1. In the software repository table, select the software image.
2. In the More actions icon to the right of the line, click Delete.

If a software image is being download to a router, you cannot delete the image until the download process completes.

## Software Upgrade

Use the Software Upgrade screen to download new software images and to upgrade the software image running on a Viptela device.

From a centralized vManage NMS, you can upgrade the software on Viptela devices in the overlay network and reboot them with the new software. You can do this for a single device or for multiple devices simultaneously.

When you upgrade a group of vBond orchestrators, vSmart controllers, and vEdge routers, the software upgrade and reboot is performed first on the vBond orchestrator, next on the vSmart controllers, and finally on the vEdge routers. For vEdge routers, up to five routers can be upgraded and rebooted in parallel at the same time.

You cannot include the vManage NMS in a group software upgrade operation. You must upgrade and reboot the vManage server by itself.

It is recommended that you perform all software upgrades from the vManage NMS rather than from the CLI.

## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Software Upgrade.
- Device List drop-down—Displays the list of devices in the overlay network. When you first open the Software Upgrade screen, Device List is selected by default.
  - WAN Edge tab bar—Includes the Controller and vManage tabs.
  - Rows Selected—Displays the number of rows selected from the table. Includes:
    - Upgrade button—Installs a new software version on the device. Includes:
    - Activate button—Reboots the device and activates the new software version.
    - Delete Available Software button—Delete a software version from a device.
    - Set Default Version button—Set a software image to be the default image on the device.
  - Device Group drop-down—List of all configured device groups in the network.
  - Table of devices in the overlay network—To re-arrange the columns, drag the column title to the desired position.
- Repository drop-down—Click Repository from the Device List drop-down to display the list of software images on the vManage or remote server.
  - Add New Software drop-down (on Repository screen)—Upload new software images to the vManage or remote server.
  - Table of software images—To re-arrange the columns, drag the column title to the desired position.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Refresh icon—Click to refresh data in the device table with the most current data.

## Maintenance

- Export icon—Click to download all data to a file, in CSV format (on Device List screen only).
- Show Table Fields icon—Click to display or hide columns from the device table. By default, all columns are displayed.

Device Group	Hostname	System IP	Chassis Number	Device Model	Current Version	Available Versions	Site ID	Reach
AP	C1111-8P	172.16.255.138	C1111-8P-FOC215124MH	vEdge 1000	16.10.514		2001	unreach
	CSR-cEdge1	172.16.255.130	CSR-97a0fe05-a03e-4a1e-afb3...	CSR1000v	16.8.372	16.8.551;16.8.414	1600	reach
	CSR-cEdge2	172.16.255.134	CSR-e109d8c2-7541-40d3-b3f...	CSR1000v	16.8.414	16.8.372	1900	reach
	ISR4221	172.16.255.139	ISR4221/K9-FOC22034WR7	ISR4221	16.10.514		2000	reach
	ISR4331-SD...	172.16.255.129	ISR4331-FD02106254L	ISR4331	16.8.436	16.8.372;16.8.414	1800	unreach
	vm1	172.16.255.11	537fcec5-00f8-4062-a894-9db...	vEdge Cloud	99.99.999-1122	99.99.999-1047	100	reach
	vm11	172.16.255.21	f3967a34-d454-49cd-8494-05c...	vEdge Cloud	99.99.999-1122	99.99.999-1047	100	reach
	vm4	172.16.255.14	3de2abff-0251-4718-b4d2-023...	vEdge Cloud	99.99.999-1122	99.99.999-1047	400	reach

## View Software Images

To view a list of software images in the repository on the vManage server or on a remote server, from the Device List drop-down, click Repository.

## Upgrade a Software Image

To upgrade the software image on a device:

1. In the title bar, click the WAN Edge, Controller, or vManage tab.
2. Select one or more devices on which to upgrade the software image.
3. Click the Upgrade button. The Software Upgrade dialog box opens.
4. Select the software version to install on the device. If the software is located on a Remote Server, select the VPN in which the software image is located.
5. To automatically activate the new software version and reboot the device, select the Activate and Reboot checkbox.
6. Click Upgrade. A progress bar indicates the status of the software upgrade.

If the control connection to the vManage NMS does not come up within the configured time limit, vManage NMS automatically reverts the device to the previously running software image. The configured time limit for all Viptela devices to come up after a software upgrade is 5 minutes, except for vEdge 100 routers, which have a default time of 12 minutes.

Note: If you upgrade the vEdge software to a version higher than that running on a controller device, a warning message is displayed that software incompatibilities might occur. It is recommended that you upgrade the controller software first, before upgrading the vEdge software.

## Activate a New Software Image

If you did not select the Activate and Reboot checkbox when upgrading the software image, the device continues to use the existing configuration. To activate the new software image:

1. In the title bar, click the vEdge, Controller, or vManage tab.
2. Select one or more devices on which to activate the new software image.
3. Click the Activate button. The Activate Software dialog box opens.
4. Select the software version to activate on the device.
5. Click Activate. vManage NMS reboots the device and activates the new software image.

If the control connection to the vManage NMS does not come up within the configured time limit, vManage NMS automatically reverts the device to the previously running software image. The configured time limit for all Viptela devices to come up after a software upgrade is 5 minutes, except for the vEdge 100 routers, which have a default time of 12 minutes.

## Delete a Software Image

To delete a software image from a Viptela device:

1. In the title bar, click the WAN Edge, Controller, or vManage tab.
2. Select one or more devices from which to delete a software image.
3. Click the Delete Available Software button. The Delete Available Software dialog box opens.
4. Select the software version to delete.
5. Click Delete.

## Set the Default Software Version

You can set a software image to be the default image on a Viptela device. Performing this operation overwrites the factory-default software image, replacing it with an image of your choosing. It is recommended that you set a software image to be the default only after verifying that the software is operating as desired on the device and in your network.

To set a software image to be the default image on a device:

1. In the title bar, click the vEdge, Controller, or vManage tab.
2. Select one or more devices on which you wish to change the default software image.
3. Click the Set Default Version button. The Set Default Version dialog box opens.
4. From the Version drop-down, select the software image to use as the default.
5. Click Set Default.

## Export Device Data in CSV Format

To export data for all devices to a file in CSV format, click the Export button. This icon, which is a downward-pointing arrow, is located to the right of the filter criteria both in the WAN Edge List and in the Controllers tab.

vManage NMS downloads all data from the device table to an Excel file in CSV format. The file is downloaded to your browser's default download location and is named `viptela_download.csv`.

## View Log of Software Upgrade Activities

To view the status of software upgrades and a log of related activities:

1. Click the Tasks icon located in the vManage toolbar. vManage NMS displays a list of all running tasks along with the total number of successes and failures.
2. Click a row to see details of a task. vManage NMS opens a status window displaying the status of the task and details of the device on which the task was performed.

## Monitor

### ACL Log

Use the ACL Log screen to view logs for access lists (ACLs) configured on a vEdge router. Routers collect ACL logs every 10 minutes.

### Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, ACL Log.
- Filter bar—Includes the Filter drop-down and time periods. Click the Filter icon to display a drop-down menu to add filters for ACL logs. Click a predefined or custom time period for which to display data.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Refresh icon—Click to refresh data in the ACL logs table with the most current data.
- Show Table Fields icon—Click to display or hide columns from the ACL logs table. By default, all columns are displayed.
- Table of ACL logs—To re-arrange the columns, drag the column title to the desired position.

The screenshot shows the vManage ACL Log screen. The interface includes a sidebar menu on the left with 'vManage' at the top and 'ACL Log' selected. The main area displays a table of ACL logs with columns for Device Name, Hostname, Entry Time, VPN, Source IP, Destination IP, Source Port, Destination Port, DSCP, Protocol, and Policy Action. A search box and filter options are visible above the table. The top bar includes navigation icons and a user profile dropdown.

Device Name	Hostname	Entry Time	VPN	Source IP	Destination IP	Source Port	Destination Port	DSCP	Protocol	Policy Action
1.1.100.33	RTP-Office	28 Apr 2017 10:...	0	76.102.35.78	66.57.61.74	1024	12347	0	17	deny
1.1.100.33	RTP-Office	28 Apr 2017 10:...	0	59.90.11.39	66.57.61.74	60014	23	0	6	deny
1.1.100.33	RTP-Office	28 Apr 2017 9:2...	0	76.102.35.78	66.57.61.74	1024	12347	0	17	deny
1.1.100.33	RTP-Office	28 Apr 2017 8:2...	0	76.102.35.78	66.57.61.74	1024	12347	0	17	deny
1.1.100.33	RTP-Office	28 Apr 2017 7:2...	0	76.102.35.78	66.57.61.74	1024	12347	0	17	deny
1.1.100.33	RTP-Office	28 Apr 2017 6:2...	0	76.102.35.78	66.57.61.74	1024	12347	0	17	deny
1.1.100.33	RTP-Office	28 Apr 2017 5:2...	0	76.102.35.78	66.57.61.74	1024	12347	0	17	deny
1.1.100.33	RTP-Office	28 Apr 2017 4:4...	0	76.102.35.78	66.57.61.74	12366	12347	0	17	deny
1.1.100.33	RTP-Office	28 Apr 2017 3:4...	0	76.102.35.78	66.57.61.74	12366	12347	0	17	deny
1.1.100.33	RTP-Office	28 Apr 2017 2:4...	0	76.102.35.78	66.57.61.74	12366	12347	0	17	deny
1.1.100.33	RTP-Office	28 Apr 2017 2:3...	0	90.82.65.154	66.57.61.74	40025	3454	2	6	deny
1.1.100.33	RTP-Office	28 Apr 2017 1:4...	0	76.102.35.78	66.57.61.74	12366	12347	0	17	deny
1.1.100.33	RTP-Office	28 Apr 2017 1:2...	0	76.102.35.78	66.57.61.74	12366	12347	0	17	deny
1.1.100.33	RTP-Office	27 Apr 2017 11:...	0	76.102.35.78	66.57.61.74	12366	12347	0	17	deny
1.1.100.33	RTP-Office	27 Apr 2017 10:...	0	76.102.35.78	66.57.61.74	12366	12347	0	17	deny
1.1.100.33	RTP-Office	27 Apr 2017 9:4...	0	76.102.35.78	66.57.61.74	12366	12347	0	17	deny

### Set ACL Log Filters

To set filters for searching ACL logs:

1. Click the Filter drop-down menu.
2. In the VPN drop-down, select the entity for which you are collecting ACL logs. You can select only one VPN.



## Monitor

- Click Search to search for logs that match the filter.

vManage NMS displays a log of activities in table format.

## Alarms

Use the Alarms screen to display detailed information about alarms generated by controllers and routers in the overlay network.

## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Alarms.
  - Email Notifications—Send email notifications when the vManage server generates alarms.
- Filter bar—Includes the Filter drop-down and time periods. Click the Filter icon to display a drop-down menu to add filters for searching alarms. Click a predefined or custom time period for which to display data.
- Alarms Histogram—Displays a graphical representation of all alarms in order of severity: Critical, Major, Medium, Minor. To hide the alarms histogram, click the Alarms Histogram title or the down angle bracket to the right of it.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Refresh icon—Click to refresh data in the alarms table with the most current data.
- Export icon—Click to download all data to a file, in CSV format.
- Show Table Fields icon—Click to display or hide columns from the alarms table. By default, all columns are displayed.
- Table of alarms—To re-arrange the columns, drag the column title to the desired position.

The screenshot displays the Cisco vManage Alarms interface. At the top, there is a navigation bar with 'Menu', 'Alarms Table', 'CloudExpress', 'Tasks', 'Alarms', 'Help', and 'User Profile'. The main content area is titled 'MONITOR | ALARMS' and includes an 'Alarms Histogram (hourly)' chart showing counts for different severity levels (Critical, Major, Medium, Minor) over time. Below the chart is a table of impacted entities with columns for Severity, Alarm Name, Message, Date & Time, and Cleared Date & Time. A search box and 'Search Options' dropdown are also visible.

Impacted Entities	Severity	Alarm Name	Message	Date & Time	Cleared Date & Time
host-name vm7001,system-ip:172.16.2...	Critical	vEdge Serial File Upload...	vEdge serial file uploaded	24 Aug 2017 12:25:03 PM PDT	---
host-name vm6001,system-ip:172.16.2...	Critical	vEdge Serial File Upload...	vEdge serial file uploaded	24 Aug 2017 12:24:59 PM PDT	---
host-name vm6002,system-ip:172.16.2...	Critical	vEdge Serial File Upload...	vEdge serial file uploaded	24 Aug 2017 12:24:56 PM PDT	---
host-name vm7008,system-ip:172.16.2...	Critical	vEdge Serial File Upload...	vEdge serial file uploaded	24 Aug 2017 12:24:54 PM PDT	---
host-name vm7001,system-ip:172.16.2...	Critical	vEdge Serial File Upload...	vEdge serial file uploaded	24 Aug 2017 12:24:02 PM PDT	---
host-name vm6001,system-ip:172.16.2...	Critical	vEdge Serial File Upload...	vEdge serial file uploaded	24 Aug 2017 12:23:58 PM PDT	---

## Set Alarm Filters

To set filters for searching alarms generated by one or more Viptela devices:

1. Click the Filter drop-down menu.
2. In the Severity drop-down, select the alarm severity level. You can specify more than one severity level.
3. In the Active drop-down, select active, cleared, or both types of alarm. Active alarms are alarms that are currently on the device but have not been acknowledged.
4. Click the Alarm Name drop-down, select the name of the alarm. You can specify more than one alarm name.
5. Click Search to search for alarms that match the filter.

vManage NMS displays the alarms both in table and graphical format.

## Export Alarm Data in CSV Format

To export data for all alarms to a file in CSV format, click the Export icon. This icon, which is a downward-pointing arrow, is located to the right of the Search box below the Alarms Histogram.

vManage NMS downloads all data from the alarms table to an Excel file in CSV format. The file is downloaded to your browser's default download location and is named `viptela_download.csv`.

## View Alarm Details

To view detailed information about any alarm:

1. Select the alarm row from the table.
2. Click the More Actions icon to the right of the row and click Alarm Details.

The Alarms Details window opens, displaying the possible cause of the alarm, impacted entities, and other details.

## Send Alarm Notifications

To send email notifications when alarms occur:

1. In the vManage Administration ► Settings screen, ensure that Email Notifications is enabled.
2. In the Monitor ► Alarms screen, click Email Notifications. A list of configured notifications is displayed in the email notifications table.
3. Click Add Email Notification.
4. In the Name field, enter a name for the email notification. The name can be up to 128 characters and can contain only alphanumeric characters.
5. In the Severity drop-down, select one or more alarm severity levels, from Critical, Major, Medium, and Minor.
6. In the Alarm Name drop-down, select one or more alarms. The alarms generated for each severity level are listed in the section Alarms Generated on vManage NMS, below.
7. In Account Details, enter the email addresses to receive email notifications:

## Monitor

- a. Click Add New Email List.
  - b. In the Email List popup, click Add Email.
  - c. Enter the email address of a user.
  - d. Add additional email addresses as desired.
  - e. Click Save.
8. In the Email Threshold field, set the maximum number of emails to be sent per minute. The number can be a value from 1 through 30. The default is 5.
  9. Click the Webhook box to trigger an HTTP callback when an alarm notification event occurs:
    - a. Enter the username and password to authenticate the webhook server.
    - b. Enter the URL of the webhook server.
  10. Select the routers to which the alarm notification applies, either All Devices or a custom list. If you select Custom, a device list is displayed:
    - a. In the Available Devices table on the left, select one or more devices.
    - b. Click the right-point arrow to move the devices to the Selected Devices table on the right.
  11. Click Add.

## View an Email Notification

1. Click Email Notifications.
2. For the desired email notification, click the View icon to the right of the row.
3. When you are done viewing the notification, click OK.

## Edit an Email Notification

1. Click Email Notifications.
2. For the desired email notification, click the Pencil icon to the right of the row.
3. When you are done editing the notification, click Update.

## Delete an Email Notification

1. Click Email Notifications.
2. For the desired email notification, click the Trash Bin icon to the right of the row.
3. In the confirmation popup, click OK.

## Alarms Generated on vManage NMS

The table below lists the alarms that the vManage NMS software generates. The software generates alarms when a state or condition changes, such as when a software component starts, transitions from down to up, or transitions from up to down. The severity indicates

## Monitor

the seriousness of the alarm. When you you create email notifications, the severity that you configure in the notification determines which alarms you can receive email notifications about.

Alarm Name	Severity	Description
AAA Admin Password Change	Critical	The password for the AAA user <b>admin</b> changed on a router or controller.
BFD Between Sites Down	Critical	All BFD sessions on all routers between two sites are in the Down state. This means that no data traffic can be sent to or transmitted between those two routers.
BFD Between Sites Up	Medium	A BFD session on a router between two sites transitioned to the Up state.
BFD Node Down	Critical	All BFD sessions for a router are in the Down state. This means that no data traffic can be sent to or transmitted from that router.
BFD Node Up	Medium	A BFD session for a router transitioned to the Up state.
BFD Site Down	Critical	All BFD sessions on all vEdge routers in a site are in the Down state. This means that no data traffic can be sent to or transmitted from that site.
BFD Site Up	Medium	A BFD session on a router in a site transitioned to the Up state.
BFD TLOC Down	Major	All BFD sessions for a TLOC (transport tunnel identified by a color) are in the Down state. This means that no data traffic can be sent to or transmitted from that transport tunnel.
BFD TLOC Up	Medium	A BFD session for a TLOC transitioned to the Up state.
BGP Router Down	Critical	All BGP sessions on a router are in the Down state.
BGP Router Up	Medium	A BGP session on a router transitioned to the Up state.
Clear Installed Certificate	Critical	All certificates on a controller or device, including the public and private keys and the root certificate, have been cleared, and the device has returned to the factory-default state.
Cloned vEdge Detected	Critical	A duplicate router that has the same chassis and serial numbers and the same system IP address has been detected.
Cloud onRamp	Major	The Cloud onRamp service was started on a router.
Control All vSmarts Down	Critical	All control connections from all vSmart controllers in the overlay network are in the Down state. This means that the overlay network cannot function.
Control Node Down	Critical	All control connections for a vEdge router are in the Down state.
Control Node Up	Medium	At least one control connection for a vEdge router transitioned to the Up State.
Control Site Down	Critical	All control connections from all Viptela devices in a site are in the Down state. This means that no control or data traffic can be sent to or transmitted from that site.
Control Site Up	Medium	A control connection from the vManage NMS and the vBond orchestrator in the site transitioned to the Up state.
Control vBond State Change	Critical Major	A control connection on a vBond orchestrator transitioned to the Down state (Critical) or the Up state (Major).
Control TLOC Down	Major	All control connections for a TLOC are in the Down state.
Control TLOC Up	Medium	A control connection for a TLOC is in the Up state.

## Monitor

Control vManage Down	Critical	All control connections from a vManage NMS are in the Down state.
Control vManage Up	Medium	A control connection from a vManage NMS transitioned to the Up state.
Control vSmart Down	Critical	All control connections from a vSmart controller in the overlay network are in the Down state.
Control vSmart Up	Medium	A control connection from a vSmart controller in the overlay network transitioned to the Up state.
Control vSmarts Up	Medium	Control connection from all vSmart controllers in the overlay network transition to the Up state.
CPU Load	Critical Medium	The CPU load on a controller or device has reached a critical level that could impair or shut down functionality, or a medium level that could impair functionality.
Default App List Update	Major	The default application and application family lists, which are used in application-aware routing policy, have changed.
Device Activation Failed	Critical	Activation of a software image on a controller or device failed.
Device Upgrade Failed	Critical	The software upgrade on a router failed.
DHCP Server State Change	Major	The state of a DHCP server changed.
Disk Usage	Critical Major	The disk usage load on a controller or device has reached a critical level that could impair or shut down functionality, or a medium level that could impair functionality.
Domain ID Change	Critical	A domain identifier in the overlay network changed.
Interface Admin State Change	Critical Medium	The administrative status of an interface in a controller or router changed from up to down (Critical) or down to up (Medium).
Interface State Change	Medium	The administrative or operational status of an interface changed.
Memory Usage	Critical Medium	The memory usage on a controller or device has reached a critical level that could impair or shut down functionality, or a medium level that could impair functionality.
New CSR Generated	Critical	A controller or router generated a certificate signing request (CSR).
OMP All vSmarts Down	Critical	All OMP connections from all vSmart controllers in the overlay network are in the Down state. This means that the overlay network cannot function.
OMP vSmarts Up		At least one OMP connection from all vSmart controllers in the overlay network is in the Up state.
OMP Node Down		All OMP connections for a vEdge router are in the Down state.
OMP Node Up	Medium	At least one OMP connection for a vEdge router is in the Up state.
OMP Site Down	Critical	All OMP connections to vSmart controllers from all nodes in the a are in the Down state. This means that that site cannot participate in the overlay network.
OMP Site Up	Medium	At least one OMP connection to vSmart controllers from all nodes in the site is in the Up state.
OMP State Change	Critical Medium	The administration or operational state of an OMP session between a vSmart controller and a vEdge router has changed, from Up to Down (Critical) or Down to Up (Medium).
OMP vSmarts Up	Medium	OMP connection from all vSmart controllers in the overlay network transition to the Up state.

## Monitor

Org Name Change	Critical	The organization name used in the certificates for all overlay network devices changed.
OSPF Router Down	Critical	All OSPF connections on a router are in the Down state.
OSPF Router Up	Medium	An OSPF connection on a router transitioned to the Up state.
PIM Interface State Change	Major	The state of a PIM interface changed.
Process Restart	Critical	A process (daemon) on a controller or router restarted.
Pseudo Commit Status	Minor	The vManage NMS has started pushing a device configuration template to a controller or router. The NMS pushes a tentative configuration (called the pseudo commit) to the device and starts the rollback timer. If, with the new configuration, the control connections between the device and the vManage NMS come up, the tentative configuration becomes permanent. If the control connections do not come up, the tentative configuration is removed, and the device's configuration is rolled back to the previous configuration (that is, to the last known working).
Root Cert Chain Installed	Critical	The file containing the root certificate key chain was installed on a controller or router.
Root Cert Chain Uninstalled	Critical	The file containing the root certificate key chain was removed from a controller or router.
Site ID Change	Critical	A site identifier in the overlay network changed.
System IP Change	Critical	The system IP address on a controller or router changed.
System IP Reuse	Critical	The same system IP address is being used by more than one device in the overlay network.
System Reboot Issued	Critical Medium	A device rebooted, either initiated by the device (Critical) or by a user (Medium).
Template Rollback	Critical	The attaching of a device configuration template to a router did not succeed in the configured rollback time, and as a result, the configuration on the device was not updated, but instead was rolled back to the previous configuration.
Unsupported SFP Detected	Critical	The software detected an unsupported transceiver in a hardware router.
vEdge Serial File Uploaded	Critical	The WAN Edge serial number file was uploaded to the vManage server.
vSmart/vManage Serial File Uploaded	Critical	A vManage NMS uploaded the file containing certificate serial numbers for the vManage NMSs and vSmart controllers in the overlay network.
ZTP Upgrade Failed	Critical	A software upgrade using ZTP failed on a controller or router.

## Additional Information

[Monitor Alarms and Events](#)

## Audit Log

Use the Audit Log screen to display a log of all activities on Viptela devices.

## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Audit Log.
- Filter bar—Includes the Filter drop-down and time periods. Click the Filter icon to display a drop-down menu to add filters for audit logs. Click a predefined or custom time period for which to display data.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Refresh icon—Click to refresh data in the audit logs table with the most current data.
- Export icon—Click to download all data to a file, in CSV format.
- Show Table Fields icon—Click to display or hide columns from the audit logs table. By default, all columns are displayed.
- Table of audit logs, displaying the time of the log, the user on the device originating the log, log message, and other details. To rearrange the columns, drag the column title to the desired position.

The screenshot shows the Cisco vManage Audit Log interface. The top bar includes the Cisco vManage logo, a navigation menu, and user profile information. The main area displays a table of audit logs with the following columns: Timestamp, User, User IP, Message, Module, Feature, and Device. The table contains 17 rows of log entries. A search box and filter options are visible above the table.

Timestamp	User	User IP	Message	Module	Feature	Device
29 Aug 2017 11:06:52 AM PDT	system	172.16.255.22	Installed root cert chain on vManage-d702d79b...	vmanage-root...	vmanage-root-ca	-
29 Aug 2017 11:06:49 AM PDT	admin	10.0.1.1	Authentication succeeded for admin@source IP:1...	user	user	172.16.255.22
29 Aug 2017 11:06:24 AM PDT	system	172.16.255.22	Installed root cert chain on vSmart-9e9f0801-c8...	vmanage-root...	vmanage-root-ca	-
29 Aug 2017 11:06:24 AM PDT	system	172.16.255.22	Installed root cert chain on vBond-268d1470-70...	vmanage-root...	vmanage-root-ca	-
29 Aug 2017 11:06:24 AM PDT	system	172.16.255.22	Transferred root cert chain file to vSmart-9e9f08...	vmanage-root...	vmanage-root-ca	-
29 Aug 2017 11:06:24 AM PDT	system	172.16.255.22	Uploaded root ca uuid list file on vBond-268d147...	vmanage-root...	vmanage-root-ca	-
29 Aug 2017 11:06:23 AM PDT	system	172.16.255.22	Transferred root ca uuid list file to vBond-268d14...	vmanage-root...	vmanage-root-ca	-
29 Aug 2017 11:06:23 AM PDT	system	172.16.255.22	Transferred root cert chain file to vBond-268d147...	vmanage-root...	vmanage-root-ca	-
29 Aug 2017 11:06:21 AM PDT	system	172.16.255.22	Installed root cert chain on vBond-268d1470-70...	vmanage-root...	vmanage-root-ca	-
29 Aug 2017 11:06:21 AM PDT	system	172.16.255.22	Installed root cert chain on vSmart-69c2099a-e5...	vmanage-root...	vmanage-root-ca	-
29 Aug 2017 11:06:21 AM PDT	system	172.16.255.22	Installed root cert chain on vSmart-9e9f0801-c8...	vmanage-root...	vmanage-root-ca	-
29 Aug 2017 11:06:21 AM PDT	system	172.16.255.22	Uploaded root ca uuid list file on vBond-268d147...	vmanage-root...	vmanage-root-ca	-
29 Aug 2017 11:06:20 AM PDT	system	172.16.255.22	Transferred root cert chain file to vManage-d702...	vmanage-root...	vmanage-root-ca	-
29 Aug 2017 11:06:20 AM PDT	system	172.16.255.22	Transferred root ca uuid list file to vBond-268d14...	vmanage-root...	vmanage-root-ca	-
29 Aug 2017 11:06:20 AM PDT	system	172.16.255.22	Transferred root cert chain file to vSmart-9e9f08...	vmanage-root...	vmanage-root-ca	-
29 Aug 2017 11:06:20 AM PDT	system	172.16.255.22	Transferred root cert chain file to vSmart-69c209...	vmanage-root...	vmanage-root-ca	-

## Set Audit Log Filters

To set filters for searching audit logs:

1. Click the Filter drop-down menu.
2. In the Module drop-down, select the entity for which you are collecting audit logs. You can select more than one entity.
3. Click Search to search for logs that match the filter.

vManage NMS displays a log of activities both in table and graphical format.

## Export Audit Log Data in CSV Format

To export data for all audit logs to a file in CSV format, click the Export icon. This icon, which is a downward-pointing arrow, is located to the right of the filter criteria.

vManage NMS downloads all data from the audit logs table to an Excel file in CSV format. The file is downloaded to your browser's default download location and is named `viptela_download.csv`.

## View Audit Log Details

To view detailed information about any audit log:

1. Select the audit log row from the table.
2. Click the More Actions icon to the right of the row and click Audit Log Details.

The Audit Log Details popup window opens, displaying details of the audit log.

## View Changes to a Configuration Template

When you push a template configuration to a device, you can view changes between the old and the new configuration template. To view changes made to a configuration template:

1. Select the audit log row from the table. The Message column of the audit log row will contain a message to the effect that the template is successfully attached to the device.
2. Click the More Actions icon to the right of the row and click CLI Diff.

The CLI Diff popup window opens, with the Config Diff tab selected by default. This window displays a side-by-side view of the differences between the configuration that was on the device and the changes made to the configuration. To view the changes inline, click the Inline Diff button located to the right of the window.

To view the updated configuration on the device, click the Configuration tab located to the left of the window.

## Events

Use the Events screen to display detailed information on events generated by Viptela devices.


## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Events.
- Filter bar—Includes the Filter drop-down and time periods. Click the Filter icon to display a drop-down menu to add filters for searching events. Click a predefined or custom time period for which to display data.
- Events Histogram—Displays a graphical representation of all events in order of severity: Critical, Major, Medium, Minor. To hide the events histogram, click the Events Histogram title or the down angle bracket to the right of it.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Refresh icon—Click to refresh data in the events table with the most current data.
- Export icon—Click to download all data to a file, in CSV format.



## Monitor

- Show Table Fields icon—Click to display or hide columns from the events table. By default, all columns are displayed.
- Table of events—To re-arrange the columns, drag the column title to the desired position.



## Set Event Filters

To set filters for searching events generated on one or more Viptela devices:

1. Click the Filter drop-down menu.
2. In the Severity drop-down, select the event severity level. Events generated by Viptela devices are collected by vManage NMS and classified as:
  - Critical—indicates that action needs to be taken immediately.
  - Major—indicates that the problem needs to be looked into but is not critical enough to bring down the network.
  - Minor—is informational only.

You can specify more than one severity level.

3. In the Component drop-down, select the configuration component that caused the event. You can select more than one configuration component.
4. In the System IP drop-down, select the system IP of the devices for which to view generated events.
5. In the Event Name drop-down, select the event name for which to view generated events. You can select more than one event name.
6. Click Search to search events that match the filter.

vManage NMS displays the events both in table and graphical format.

## Export Event Data in CSV Format

To export data for all events to a file in CSV format, click the Export icon. This icon, which is a downward-pointing arrow, is located to the right of the Search box below the Events Histogram.

vManage NMS downloads all data from the events table to an Excel file in CSV format. The file is downloaded to your browser's default download location and is named `viptela_download.csv`.

## View Device Details

To view detailed information about a device on which an event was generated:

1. Select the event row from the table.
2. Click the More Actions icon to the right of the row and click Device Details.

The Device Details popup window opens, displaying the hostname of the device originating the event and other details.

## Geography

Use the Geography screen to view information about the Viptela devices and links in the overlay network. The Geography screen provides a map displaying the geographic location of the Viptela devices.

Note: The browser on which you are running vManage NMS must have Internet access. If you do not have Internet access, ensure that the browser has access to `"*.openstreetmaps.org."`

## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Geography.
  - No Geographic Coordinates—Located to the right of the title bar, it displays the number of devices for which geographic coordinates are not configured.
- Filter bar—Includes the Filter button and the following tabs which reflect the default Filter selections:
  - All Groups for the device group.
  - vEdge, vEdge-vBond, vBond, vSmart, and vManage for the device types.
  - Control Up, Data Up, and Data Down for the link states.
- Map—Displays the geographic location of Viptela devices based on the latitude and longitude configured on the devices. The map includes the following elements:
  - Search box—Includes the Search Options drop-down, for a Contains or Match string. The search applies to all devices, including those that have no geographic coordinates defined.
  - + (plus) and – (minus) zoom icons.
  - Map provider icon, to choose any open source map provider.
  - Device icons for the Viptela devices:



## Monitor



vSmart




vEdge



vBond

- Device clusters—A green circle with a number in the center indicates a cluster of devices located in an area. Click the cluster to display the individual device icons on the map.



## Set Map Filters

To select the devices and links you want to display on the map:

1. Click the Filter button to display a pull-down menu.
2. Select the device group from the pull-down menu which includes all configured device groups. By default, the group "All" is selected and displays all Viptela devices in the overlay network. The group "No Groups" includes the devices that are not part of a device group. If all devices are in a group, the "No Groups" group is not displayed.
3. Select the Viptela devices to display on the map. By default, the map displays all device types including vEdge, vEdge-vBond, vSmart, and vManage.
4. Select the state of control and data links. By default, the map displays all control and data connections.
5. Close the Filter box by moving the cursor outside the box.

The map is dynamically updated to reflect your selections. Also, as you make the device group, device type, and link selections, the tabs next to the Filter button are updated.

## View Device Information

To display basic information for a device, hover over the device icon. A hover box displays the system IP, hostname, site ID, device type, and device status.

To display detailed information for a device, double-click the device icon to open the View More Details hover box. Click Device Dashboard, Device Details, SSH Terminal, or Links to get further details for the device.

## View Link Information

By default, control and data connections are not displayed on the map. To see control and data connections for a device:

1. Double-click the device icon to open a hover box with details about the device.
2. Click Links.

Note the following:

- An active control connection between two devices is displayed on the map as a thin blue line. Multiple active connections between devices are displayed by a bold blue line. A control connection that is down is displayed on the map as a dotted red line. Multiple control connections that are down are displayed by a bold dotted red line. If you hover over the line, a hover box tells you if the connection is up or down.
- An active data connection between two devices is displayed on the map as a thin green line. Multiple active data connections are displayed by a bold green line. A data connection that is down is displayed on the map as a dotted red line. Multiple data connections that are down are displayed by a bold dotted red line. If you hover over the line, a hover box tells you if the connection is up or down.
- An active consolidated control and data connection between two devices is displayed on the map as a thick grey line.

## Configure Geographic Coordinates for a Device

To configure the geographic coordinates for a device, use the Configuration ► Templates ► System feature template.

If the Viptela device is not attached to a configuration template, you can configure the latitude and longitude directly on the device:

1. Select the Tools ► SSH Terminal screen.
2. Select the device from the left pane. The SSH Terminal screen opens in the right pane.
3. Enter the username and password to log in to the device.
4. Determine whether the device is attached to a configuration template:

```
Viptela# show system status
```

Check the values in the vManaged and Configuration template output fields. For example:

```
...
```

```
Personality:    vedge
Model name:    vedge-cloud
Services:      None
vManaged:     false
Commit pending: false
Configuration template: None
```

If the vManaged field is false, the device is not attached to a configuration template, and the Configuration template field says None. For such a device, you can configure the GPS coordinates directly from the CLI.

## Monitor

If the vManaged field is true, the device's configuration has been downloaded by the vManage server, and the Configuration template field shows the name of the configuration template. For such a device, you cannot configure the GPS coordinates directly from the CLI. If you attempt to do so, the **validate** or **commit** command fails, with the following message:  
Aborted: 'system is-vmanaged': This device is being managed by the vManage. Configuration through the CLI is not allowed.

5. Enter configuration mode:  
Viptela# **config**  
Viptela(config)#
6. Configure the latitude and longitude on the device:  
Viptela(config)# **system gps-location latitude** *degrees.minutes.seconds*  
Viptela(config-system)# **gps-location longitude** *degrees.minutes.seconds*
7. Save the configuration:  
Viptela(config-system)# **commit**  
Viptela(config-system)#

## Network

Use the Network screen to display a list of Viptela devices in the overlay network and to display detailed information about individual devices.

## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Network.
- Device Groups drop-down—Lists all configured device groups in the network.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Refresh icon—Click to refresh data in the device table with the most current data.
- Export icon—Click to download all data to a file, in CSV format.
- Show Table Fields icon—Click to display or hide columns from the device table. By default, all columns are displayed.
- Table of devices in the overlay network—To re-arrange the columns, drag the column title to the desired position.

The screenshot shows the Cisco vManage interface with the 'Monitor | NETWORK' view. A table lists various devices with their status and configuration details. A blue arrow points to the 'Devices Table' label above the table.

Hostname	State	System IP	Reachability	Site ID	Device Model	BFD	Control	Version	Up Since
vm1	✓	172.16.255.11	reachable	100	vEdge Cloud	1 (3)	3	99.99.999-5247	16 Aug 2017 11:38:00
vm10	✓	172.16.255.20	reachable	200	vSmart	-	7	99.99.999-5247	16 Aug 2017 5:08:00
vm11	✓	172.16.255.21	reachable	100	vEdge Cloud	1 (3)	3	99.99.999-5247	16 Aug 2017 5:08:00
vm12	✓	172.16.255.22	reachable	200	vManage	-	7	99.99.999-6025	16 Aug 2017 5:07:00
vm16	✓	172.16.255.26	reachable	-	vEdge Cloud (vilo...	-	-	99.99.999-5247	16 Aug 2017 5:08:00
vm4	✓	172.16.255.14	reachable	400	vEdge Cloud	2 (4)	3	99.99.999-5247	16 Aug 2017 5:08:00
vm5	✓	172.16.255.15	reachable	500	vEdge Cloud	0	3	99.99.999-5247	16 Aug 2017 5:08:00
vm6	✓	172.16.255.16	reachable	600	vEdge Cloud	0	3	99.99.999-5247	16 Aug 2017 5:08:00
vm9	✓	172.16.255.19	reachable	100	vSmart	-	7	99.99.999-5247	16 Aug 2017 5:08:00

## View List of Devices

The Network screen lists the Viptela devices in the overlay network. When you first come to the Network screen, the device group "All" is selected, and the screen shows status information for all Viptela devices in the overlay network.

To see a list of devices in a particular group, select that device group.

To filter the devices by reachability, hostname, system IP address, site ID, and device model, select from the sort options in the drop-down or type a string in the Search box.

To display information about an individual device, click its hostname.

## Export Device Data in CSV Format

To export data for all devices to a file in CSV format, click the Export button. This button is located to the right of the filter criteria.

vManage NMS downloads all data from the device table to an Excel file in CSV format. The file is downloaded to your browser's default download location and is named viptela\_download.csv.

## View Information about a Device

To view high-level information about a device, select the device from the Monitor ► Network screen:

1. From the Device Groups drop-down list, select the device group to which the device belongs. The device table lists all the devices in the selected group.
2. Select the device by clicking its hostname. The left pane lists the information categories about the device. In the right pane, the System Status category is selected, which displays status information about the device.


To select a different device, either click the Select Device drop-down located at the top of the left pane, or click Network in the title bar and then select a device by clicking its hostname.

---

## Monitor

After you select a device by clicking its hostname, the screen changes and displays the following elements:

- Select Device bar—A horizontal bar that includes these elements:
  - Select Device drop-down
  - Device name
  - Device IP address
  - Device site location
  - Device model
  - More Info drop-down
- Left pane—A vertical pane that lists the categories of information you can display about the device:
  - Applications—DPI flow information.
  - Interface—Interface status and statistics.
  - TCP Optimization—Statistics related to fine-tuning the processing of TCP data traffic.
  - WAN—TLOC and tunnel status and statistics.
  - Control Connections—Status and statistics for control connections.
  - System Status—Reboot and crash information, hardware component status, and CPU and memory usage.
  - Events—Latest syslog events.
  - ACL Logs—Logging files for access lists (ACLs).
  - Troubleshooting—Ping and traceroute traffic connectivity tools.
  - Real Time—Real-time device information for feature-specific operational commands.
- Right pane—Displays information about the selected category.



## View Device Status Summary

To view summary status information about a device:

1. From the Monitor ► Network screen, select a device.
2. From the Select Device bar, click the More Info drop-down located to the right of the bar. vManage NMS opens a drop box with summary information about the device.

To close the device status summary, click More Info again or click anywhere on the screen outside the drop-down.

## View DPI Flows

To view DPI flow information on a vEdge router:

1. From the Monitor ► Network screen, select a device.
2. Click Applications in the left pane. The right pane displays DPI flow information for the device.

The upper part of the right pane contains:

- Filter bar—Located directly under the device name, this bar includes the Filter icon and time periods. Click the Filter icon to display a drop-down menu to select the desired VPN and TLOC. Click a predefined or custom time period for which to display data.
- DPI flow information in graphical format.



## Monitor

- DPI flow graph legend—Select an application family to display information for just that flow. Click the Total Network Traffic checkbox to display flow information as a proportion of total network traffic.

The lower part of the right pane contains:

- Filter criteria.
- DPI flow information table that lists all application families sorted by usage. By default, the top six application families are selected. The graphical display in the upper part of the right pane plots the flow and usage of the selected application families.
  - Click the checkbox to the left to select and deselect application families. You can select and display information for a maximum of six application families at one time.
  - Click an application family to display applications within the family.
  - Click an application to display the source IP addresses of the devices accessing the application. The Traffic per TLOC pie chart next to the graph displays traffic distribution per TLOC (color).
  - To re-arrange the columns, drag the column title to the desired position.
  - To return to the list of application families, click Applications in the title bar or click the Back button in the browser.

## View Interfaces

To view information about interfaces on a device:

1. From the Monitor ► Network screen, select a device.
2. Click Interface in the left pane. The right pane displays interface information for the device.

The upper part of the right pane contains:

- Chart Options bar—Located directly under the device name, this bar includes:
  - Chart Options drop-down—Click Chart Options to select the type of data to display.
  - IPv4 & IPv6 drop-down—Click IPv4 & IPv6 to select the type of interfaces to display. The information is displayed in graphical format. By default, the graph is Combined, showing interfaces on which both IPv4 and IPv6 addresses are configured. To display IPv4 and IPv6 interfaces in separate graphs, select the Separated toggle button.
  - Time periods—Click either Real Time, a predefined time period, or a custom time period for which to display data.
- Interface information in graphical format.
- Interface graph legend—Select an interface to display information for just that interface.

The lower part of the right pane contains:

- Filter criteria.
- Interface table that lists information about all interfaces. By default, the first six interfaces are selected. The graphical display in the upper part of the right pane plots information for the selected interfaces.
  - Click the checkbox to the left to select and deselect interfaces. You can select and display information for a maximum of 30 interfaces at one time.
  - To re-arrange the columns, drag the column title to the desired position.
  - For cellular interfaces, click the interface name to display a screen that shows detailed information about the cellular interface.

## View TCP Optimization Information

If TCP optimization is enabled on a router, you can view information about how the optimization is affecting the processing and throughput of TCP data traffic on the router:

1. From the Monitor ► Network screen, select a vEdge router.
2. Click TCP Optimization—WAN Throughput in the left pane. The right pane displays the WAN throughput, in megabits per second.

The upper part of the right pane contains the following elements:

- Chart Options bar—Located directly under the device name, this bar includes the Filter Options drop-down and time periods. Click Filter to limit the data to display based on VPN, local TLOC color, destination IP address, remote TLOC color, and remote system IP address. Click a predefined or custom time period for which to display data.
- Average optimized throughput information in graphical format.
- WAN graph legend—Identifies non-optimized and TCP optimized packet throughput.

The lower part of the right pane shows the hourly average throughput and the total optimized throughput, both in megabits per second.

Click TCP Optimization—Flows in the left pane to display information about TCP-optimized traffic flows. The upper part of the right pane contains the following elements:

- Chart Options bar—Located directly under the device name, this bar includes the Filter drop-down and time periods. Click Filter to limit the data to display based on VPN, local TLOC color, destination IP address, remote TLOC color, and remote system IP address. Click a predefined or custom time period for which to display data.
- Average optimized throughput information in graphical format.
- Flows graph legend—Identifies traffic flows.

The lower part of the right pane contains the following elements:

- Set perspective—Select the flow direction.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Flow table that lists the flow destination, usage, and percentage of total traffic for all TCP-optimized flows. By default, the first six flows are selected. Click the checkbox to the left to select and deselect flows to display. The graphical display in the upper part of the right pane plots information for the selected flows.

Click TCP Optimization—Connections in the left pane to display status information about all the tunnels over which the most TCP-optimized traffic is flowing. The upper part of the right pane contains the following elements:

- TCP Optimization Connections in graphical format
- Connection State boxes—Select the connection state or states to display TCP optimization information about.

The lower part of the right pane contains the following elements:

- Filter criteria.
- Flow table that lists information about each of the tunnels, including the tunnel's connection state.

## View TLOC Loss, Latency, and Jitter Information

To view information about TLOC loss, latency, and jitter:

1. From the Monitor ► Network screen, select a device.

## Monitor

2. Click WAN–TLOC in the left pane. The right pane displays the aggregated average loss or latency/jitter information for all TLOC colors.

The upper part of the right pane contains the following elements:

- Chart Options bar—Located directly under the device name, this bar includes the Chart Options drop-down and time periods. Click Chart Options to select the type of data to display. Click a predefined or custom time period for which to display data.
- TLOC information in graphical format. The time interval in the graph is determined by the value of the BFD application-aware routing [poll interval](#).
- TLOC graph legend—Select a TLOC color to display information for just that TLOC.

The lower part of the right pane contains the following elements:

- Search box—Includes the Search Options drop-down, for a Contains or Match.
- TLOC color table that lists average jitter, loss, and latency data about all TLOCs. By default, the first six colors are selected. The graphical display in the upper part of the right pane plots information for the selected interfaces.
  - Click the checkbox to the left to select and deselect TLOC colors. You can select and display information for a maximum of 30 TLOCs at one time.
  - Click Application Usage to the right to display DPI flow information for that TLOC.

## View Tunnel Connections

To view all tunnel connections for a device:

1. From the Monitor ► Network screen, select a device.
2. Click WAN–Tunnel in the left pane. The right pane displays information about all tunnel connections.

The upper part of the right pane contains the following elements:

- Chart Options bar—Located directly under the device name, this bar includes the Chart Options drop-down and time periods. Click Chart Options to select the type of data to display. Click a predefined or custom time period for which to display data.
- Tunnel information in graphical format.
- Tunnel graph legend—Select a tunnel to display information for just that tunnel.

The lower part of the right pane contains the following elements:

- Search box—Includes the Search Options drop-down, for a Contains or Match.
- Tunnel table that lists average latency, loss, and jitter data about all tunnel end points. By default, the first six tunnels are selected. The graphical display in the upper part of the right pane plots information for the selected tunnels.
  - Click the arrow to the left to view the tunnel end points for that TLOC color.
  - Click the checkbox to the left to select and deselect tunnels. You can select and display information for a maximum of 30 tunnels at one time.
  - Click Application Usage to the right to display DPI flow information for that TLOC.

## View WiFi Configuration

To view WiFi configuration for Viptela routers that support wireless LANs (WLANs), such as the vEdge 100wm routers:

1. From the Monitor ► Network screen, select a device.

---

## Monitor

2. Click WiFi in the left pane. The right pane displays information about WiFi configuration on the router.

The upper part of the right pane contains the following elements:

- AP Information bar—Located directly under the device name, it displays access point information and the Clients Details button. Click the Clients Details button to view information about clients connected to the WiFi access point during the selected time period.
- Radio frequency parameters for access points.
- SSID parameters for virtual access points (VAPs).

The lower part of the right pane contains the following elements:

- VAP receive and transmit statistics bar—Includes the time periods. Click a predefined or custom time period for which to display data.
- VAP receive and transmit statistics information in graphical format.
- VAP statistics graph legend—Select a VAP interface to display information for just that interface. Click the VAP interface again to return to the previous display.

### View Client Details

To view details of clients connected to the WiFi access point, click the Clients Details button on the WiFi screen.

The upper part of the Clients Info right pane contains the following elements:

- Clients Details title bar—Includes the Clients Usage tab.
- Time periods—Click a predefined or custom time period for which to display data.
- Information of clients connected to the WiFi access point in graphical format. Select a column to display information for just those clients in tabular format in the lower part of the screen.

The lower part of the Clients Info right pane contains the following elements:

- Filter criteria.
- Table of clients connected to the WiFi access point.

### View Client Usage

To view data usage details of all clients connected to the WiFi access point, click the Clients Usage tab.

The upper part of the Clients Usage right pane contains the following elements:

- Time periods—Click a predefined or custom time period for which to display data.
- Data usage of all clients connected to the WiFi access point in graphical format.
- Data usage information graph legend—Select a client MAC address to display information for just that client.

The lower part of the Clients Usage right pane contains the following elements:

- Filter criteria.
- Data usage information table. By default, the first six clients are selected.

## View Control Connections

To view all control connections for a device:

1. From the Monitor ► Network screen, select a device.  
If you select a controller device—a vBond orchestrator, a vManage NMS, or a Smart controller—the Control Connections screen opens by default.
2. If you select a vEdge router, click Control Connections in the left pane. The right pane displays information about all control connections that the device has with other controller devices in the network.

The upper part of the right pane contains the following elements:

- Expected and actual number of connections.
- Control connection data in graphical format. If the device has multiple interfaces, vManage NMS displays a graphical topology of all control connections for each color.

The lower part of the right pane contains the following elements:

- Search box—Includes the Search Options drop-down, for a Contains or Match.
- Control connections data in tabular format. By default, the first six control connections are selected. The graphical display in the upper part of the right pane plots information for the selected control connections.
  - Click the arrow to the left to view the control connections for that TLOC color.
  - Click the checkbox to the left to select and deselect control connections. You can select and display information for a maximum of six control connections at one time.

## View System Status

To view system status about a device:

1. From the Monitor ► Network screen, select a device.  
When you select a vEdge router, the System Status screen opens by default.
2. Click System Status in the left pane. The right pane displays information about the device.

The right pane contains the following elements:

- Reboot—Number of times the device has rebooted. For details about each reboot, click Reboot. The Reboot screen opens and contains the following elements:
  - Search box—Includes the Search Options drop-down, for a Contains or Match.
  - Table listing all the reboots on the device along with the time and reason for the reboot. If the device is down for 90 seconds or longer, the reason shows as "Unknown". The Last Updated column displays the time when the vManage NMS retrieved the reboot data from the device.
- Crash—Number of times the device has crashed. For details about each crash, click Crash. The Crash screen opens and contains the following elements:
  - Search box—Includes the Search Options drop-down, for a Contains or Match.
  - Table listing all the crashes on the device along with the time of crash and name of the core file created as a result of the crash.
- Status of hardware components, applicable only if the selected device is a hardware vEdge router:
  - Module

## Monitor

- Temperature sensors
- USB
- Power supply
- Fans

The status of a hardware component is represented in one of the following ways:

- Green check mark—Component is operational.
- Red circle with an X—Component is down.
- Orange triangle with an exclamation point—Component has an error.
- N/A—Not applicable since the selected device is not a hardware vEdge router.
- CPU & Memory—To the right are the time periods. Click a predefined or custom time period for which to display data.
  - CPU usage—Displays the CPU usage, as a percentage of available CPU, over the selected time range.
  - Memory usage—Displays the memory usage, as a percentage of available memory, over the selected time period.

## View Events

To view the number of critical, major, or minor events on a device:

1. From the Monitor ► Network screen, select a device.
2. Click Events in the left pane. The right pane displays information about all events on the device.

The upper part of the right pane contains the following elements:

- Filter bar—Includes the Filter drop-down and time periods. Click the Filter icon to display a drop-down menu to add filters for searching events by severity, component, and event name. Click a predefined or custom time period for which to display data.
- Events Histogram—Displays a graphical representation of all events. To hide the events histogram, click the Events Histogram title or the down angle bracket to the right of it.

The lower part of the right pane has the following elements:

- Search box—Includes the Search Options drop-down, for a Contains or Match.
- Events table.
  - To re-arrange the columns, drag the column title to the desired position.
  - To change the sort order in a column, click the Up or Down arrow in the column title.

## View ACL Logs

To view logs for access lists (ACLs) configured on a vEdge router:

1. From the Monitor ► Network screen, select a vEdge router.
2. Click ACL Logs in the left pane. The right pane displays information about all localized data policy (ACL) logs on the router. You configure these logs by including the **log** action in an ACL.

## Monitor

The upper part of the right pane contains the following elements:

- Filter bar—Includes the Filter drop-down and time periods. Click the Filter icon to display a drop-down menu to add filters for searching logs by VPN. Click a predefined or custom time period for which to display data.
- Search box—Includes the Search Options drop-down, for a Contains or Match.

The lower part of the right pane contains the following elements:

- Logs table.
  - To re-arrange the columns, drag the column title to the desired position.
  - To change the sort order in a column, click the Up or Down arrow in the column title.

## Troubleshoot a Device

You can troubleshoot connectivity or traffic health for all devices in the overlay network.

### Check Device Connectivity

To troubleshoot connectivity for a device in the network, you can do the following:

- Check device bringup
- Ping the device
- Run a speed test
- Run a traceroute
- View control connections in real time

### Check Device Bringup

To verify the status of a device bringup (available on vEdge routers only):

1. From the Monitor ► Network screen, select the device.
2. Click Troubleshooting in the left pane.
3. From the Connectivity pane, click Device Bringup.

The Device Bringup screen opens and displays:

- Troubleshooting drop-down—Located to the right of the Select Device drop-down. Click an option to view troubleshooting information. To close the drop-down, click the Troubleshooting button again.
- Device bringup state—Indicated by one of the following states:
  - Green check mark—Indicates that the device has successfully established control-plane connections with the controller devices in the network and is up and running.
  - Gray check mark—Indicates that ZTP was disabled in the Administration ► Settings screen when the device initially came up. You will see this state for the Software Image Update box only.

## Monitor

- Red check mark—Indicates that the device failed to establish control-plane connections with the controller devices in the network and is not up and running.
- Yellow exclamation point—Indicates that vManage NMS could not find the reason for a failure on the device.

### Ping a Device

To verify that a device is reachable on the network, ping the device to send ICMP ECHO\_REQUEST packets to it:

1. From the Monitor ► Network screen, select the device.
2. Click Troubleshooting in the left pane.
3. From the Connectivity pane, click Ping.
4. In the Destination IP field, enter the IP address of the device to ping.
5. In the VPN drop-down, select the VPN to use to reach the device.
6. In the Source/Interface drop-down, select the interface to use to send the ping packets.
7. In the Probes field, select the protocol type to use to send the ping packets.
8. In the Source Port field, enter the number of the source port.
9. In the Destination Port field, enter the number of the destination port.
10. In the Type of Service field, enter the value for the type of service (ToS) field to include in the ping packets.
11. In the Time to Live field, enter the round-trip time for sending this ping packet and receiving a response, in milliseconds.
12. Click the Don't Fragment slider to set the Don't Fragment bit in the ping packets.
13. Click Advanced Options to specify additional parameters:
  - a. In the Count field, enter the number of ping requests to send. The range is 1 through 30. The default is 5.
  - b. In the Payload Size field, enter the size of the packet to send. The default is 64 bytes, which comprises 56 bytes of data and 8 bytes of ICMP header. The range for data is 56 through 65507 bytes.
  - c. Click the Rapid slider to send 5 ping requests in rapid succession and to display statistics only for packets transmitted and received, and the percentage of packets lost.
14. Click Ping.

### Run a Speed Test

To check the actual bandwidth of a circuit from one device to another:

1. In the Administration ► Settings screen, ensure that Data Stream is enabled.
2. From the Monitor ► Network screen, select the device.
3. Click Troubleshooting in the left pane.
4. From the Connectivity pane, click Speed Test.
5. In the Source Circuit drop-down, select the color of tunnel interface on the local device.



## Monitor

6. In the Destination Device drop-down, select the remote device by the device's name and system IP address.
7. In the Destination Circuit drop-down, select the color of the tunnel interface on the remote device.
8. Click Start Test. The speed test sends a single packet from the source to the destination and receives the acknowledgement from the destination.

The middle part of the right pane reports the results of the speed test. The clock reports the circuit's speed based on the round-trip time. The download speed shows the speed from the source to the destination, and the upload speed shows the speed from the destination to the source, both in Mbps. The configured downstream and upstream bandwidths for the circuit are also displayed.

When a speed test completes, the test results are added to the table at the lower part of the right pane.

## Run a Traceroute

To display the path that packets take to reach a host or IP address on the network:

1. From the Monitor ► Network screen, select the device.
2. Click Troubleshooting in the left pane.
3. From the Connectivity pane, click Trace Route.
4. In the Destination IP field, enter the IP address of a device on the network.
5. In the VPN drop-down, select the VPN to use to reach the device.
6. In the Source/Interface drop-down, select the interface to use to send traceroute probe packets.
7. Click Advanced Options.
8. In the Size field, enter the size of the traceroute probe packets, in bytes.
9. Click Start to trigger a traceroute to the requested destination.

The lower part of the right pane displays:

- Output—Raw output of the path the traceroute probe packets take to reach the destination.
- Graphical depiction of the path the traceroute probe packets take to reach the destination.

## View Control Connections in Real Time

To display a real-time view the control plane connections on a vEdge router:

1. From the Monitor ► Network screen, select the device. The device must be a vEdge router.
2. Click Troubleshooting in the left pane.
3. From the Connectivity pane, click Control Connections.

The control plane connection screen is updated automatically, every 15 seconds.

The upper part of the right pane shows figures illustrates the operational control plane tunnels between the vEdge router and vManage and vSmart controllers.

The lower part of the lower pane contains a table that shows details for each of the control plane tunnels, including the remote device's IP address and the status of the tunnel end points, including the reason for the failure of an end point.

## Check Traffic Health

To check traffic health for a vEdge router in the network:

- View tunnel health
- View traffic path information
- Packet capture
- Simulate flows

## View Tunnel Health

To view the health of a tunnel from both directions (available on vEdge routers only):

1. From the Monitor ► Network screen, select the device.
2. Click Troubleshooting in the left pane.
3. From the Traffic pane, click Tunnel Health.
4. From the Local TLOC drop-down, select a source TLOC.
5. From the Remote Device drop-down, select a remote device.
6. From the Remote TLOC drop-down, select a destination TLOC.
7. Click Go. The lower part of the screen displays:
  - Chart Options bar—Located directly under the device name, this bar includes the Chart Options drop-down and time periods. Click Chart Options to select the type of data to display. Click a predefined or custom time period for which to display data.
  - App-route data (either loss, latency, or jitter) in graphical format for all tunnels between the two devices in each direction.
  - App-route graph legend—Identifies selected tunnels from both directions.

Select a TLOC to display information for just that TLOC.

## Check Application-Aware Routing Traffic

To check application-aware routing traffic from the source device to the destination device (available on vEdge routers only):

1. From the Monitor ► Network screen, select the device.
2. Click Troubleshooting in the left pane.
3. From the Traffic pane, click App Route Visualization.
4. From the Remote Device drop-down, select a destination device.
5. Click Go. The lower part of the screen displays:
  - Chart Options bar—Located directly under the device name, this bar includes the Chart Options drop-down and time periods. Click Chart Options to select the type of data to display. Click a predefined or custom time period for which to display data.
  - Application-aware routing data (either loss, latency, or jitter), along with octets, in graphical format for all tunnels between the two devices.

## Monitor

- Application-aware routing graph legend—Identifies source and destination TLOC.

### Capture Packets

To capture control plane and data plane packets in real time, similar to a UNIX tcpdump operation, and to save these packets to a file (available on vEdge routers only):

1. From the Monitor ► Network screen, select the device.
2. Click Troubleshooting in the left pane.
3. From the Traffic pane, click App Packet Capture.
4. From the VPN drop-down, select the VPN in which to capture packets.
5. From the Interface drop-down, select the interface over which to capture packets.
6. Optionally, click Traffic Filter to filter the packets to capture based on values in their IP headers. Enter values for one or more of these fields:
  - a. In Source IP, enter the packets' source IP address.
  - b. In Source Port, enter the packets' source port number.
  - c. In Protocol, enter the packets' protocol number
  - d. In Destination IP, enter the packets' destination IP address.
  - e. In Destination Port, enter the packets' destination port number.
7. Click Start. The packet capture begins, and displays its progress:
  - a. Packet Capture in Progress—Packet capture stops after 5 minutes, after the file of collected packets reaches 5 MB, or when you click the Stop button.
  - b. Preparing file to download—vManage NMS creates a file in libpcap format (a.pcap file).
  - c. File ready, click to download the file—Click the download icon to download the generated file.

### Simulate Flows

To display the next-hop information for an IP packet (available on vEdge routers only):

1. From the Monitor ► Network screen, select the vEdge router.
2. Click Troubleshooting in the left pane.
3. From the Traffic pane, click Simulate Flows.
4. To specify the data traffic path, select values or enter data in the required fields (marked with an asterisk [\*]) and optional fields. The required fields are:
  - VPN—VPN in which the data tunnel is located.
  - Source Interface—Interface from which the cflowd flow originates.
  - Source IP—IP address from which the cflowd flow originates.
  - Destination IP—Destination IP address of the cflowd flow.
  - Protocol (under Advanced Options)—Number of the protocol being used to transmit the cflowd flow.The optional fields are:
  - Application—Application running on the router.
  - Source Port (under Advanced Options)—Port from which the cflowd flow originates.

## Monitor

- Destination Port (under Advanced Options)—Destination port of the cflowd flow.
  - DSCP (under Advanced Options)—DSCP value in the cflowd packets.
5. Click Advanced Options:
    - a. In the Path toggle field, select whether the data traffic path information comes from the service side of the router or from the tunnel side.
    - b. Select values or enter data in the required fields (marked with an asterisk [\*]) and optional fields. The required fields are:
      - Protocol—Number of the protocol being used to transmit the cflowd flow.
 The optional fields are:
      - Source Port—Port from which the cflowd flow originates.
      - Destination Port—Destination port of the cflowd flow.
      - DSCP—DSCP value in the cflowd packets.
    - c. Check the All Paths checkbox to display all possible paths for a packet.
  6. Click Simulate to determine the next hop that a packet with the specified headers would take.

## Check Device Syslog Files

To display the contents of a device's syslog files:

1. In the Administration ► Settings screen, ensure that Data Stream is enabled.
2. From the Monitor ► Network screen, select the vEdge router.
3. Click Troubleshooting in the left pane.
4. From the Logs pane, click Debug Log.
5. In the Log Files field, select the name of the log file. The lower part of the screen displays the log information.

## View Real-Time Data

To view real-time data for a device:

1. From the Monitor ► Network screen, select a device.
2. Click Real Time. The right pane displays system information about the device.

The right pane contains the following elements:

- Command drop-down—Located directly under the device name, this drop-down allows you to select a feature-specific operational command to display real-time device information for the selected command. The commands in the drop-down are listed alphabetically. The commands available vary depending on the device selected. When you first select Real Time, the System Information command is selected, and real-time system information about the device is displayed in tabular format. For some commands, you can add filters to speed up the display of information. When you select these commands from the drop-down, the Select Filter window is displayed prompting you to either Show Filters or Do Not Filter.
  - Show Filters—Displays the available filters. Fill in the desired fields and click Search to display real-time device information corresponding just to those fields. Clicking Search without filling any of the fields displays the entire information for the selected command.
  - Do Not Filter—Displays the entire real-time device information for the selected command.
- Filter criteria.

## Monitor

- Table with real-time information for the selected command.
  - To re-arrange the columns, drag the column title to the desired position.
  - To change the sort order in a column, click the Up or Down arrow in the column title.

## Tools

### Operational Commands

Use the Operational Commands screen to run, on Viptela devices, a group of two or more operational commands as a single command.

### Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Operational Commands.
  - Show Admin Tech List button—Click to display a list of all requests to generate admin-tech file.
- Device Groups drop-down—Lists all configured device groups in the network.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Refresh icon—Click to refresh data in the device table with the most current data.
- Show Table Fields icon—Click to display or hide columns from the device table. By default, all columns are displayed.
- Table of devices in the overlay network—To re-arrange the columns, drag the column title to the desired position.

The screenshot displays the 'Operational Commands' screen in Cisco vManage. The interface includes a top navigation bar with the Cisco vManage logo and user profile 'admin'. A left sidebar provides navigation options such as Dashboard, Monitor, Configuration, Tools, SSH Terminal, Rediscover Network, Operational Commands, Maintenance, Administration, and vAnalytics. The main content area is titled 'TOOLS | OPERATIONAL COMMANDS' and contains a 'Devices Table'. The table has columns for Hostname, System IP, Device Model, Chassis Number/ID, State, Reachability, Site ID, and BFD. A 'Show Admin Tech List' button is located in the top right corner of the table area. A blue arrow points to the 'Devices Table' title.

Hostname	System IP	Device Model	Chassis Number/ID	State	Reachability	Site ID	BFD
C1111-8P	172.16.255.138	vEdge 1000	C1111-8P-FOC215124MH	⊖	unreachable	2001	—
CSR-cEdge1	172.16.255.130	CSR1000v	CSR-97a0fe05-a03e-4a1c-afb3-4f9...	⊕	reachable	1500	5
CSR-cEdge2	172.16.255.134	CSR1000v	CSR-e109dbc2-7541-40d3-b3f7-36...	⊕	reachable	1900	5
ISR4221	172.16.255.139	ISR4221	ISR4221/K9-FOC22034WR7	⊕	reachable	2000	5
ISR4331-SDWAN-2	172.16.255.129	ISR4331	ISR4331-FD02106254L	⊖	unreachable	1800	—
vm1	172.16.255.11	vEdge Cloud	537fcec5-00f8-4062-e894-9db7d1...	⊕	reachable	100	4
vm10	172.16.255.20	vSmart	122413d5-c347-40fc-9fac-83c24f...	⊕	reachable	200	—
vm11	172.16.255.21	vEdge Cloud	f3967a34-d454-49cd-8494-05c73d...	⊕	reachable	100	4
vm12	172.16.255.22	vManage	9316710e-0324-4a4f-8b8f-6a1f80...	⊕	reachable	200	—
vm16	172.16.255.26	vEdge Cloud (vBo...	81682a0b-1385-4092-9c6d-58f0e7...	⊕	reachable	—	—
vm4	172.16.255.14	vEdge Cloud	3de2abff-0251-4718-b4d2-023d2d...	⊕	reachable	400	5
vm9	172.16.255.19	vSmart	34002ebe-d212-423d-8c83-f4387c...	⊕	reachable	100	—

## Admin Tech Command

Use the Admin Tech command to collect system status information for a device in a tar file, to aid in troubleshooting and diagnostics.

1. From the device table, select the device.
2. Click the More Actions icon to the right of the row and click Admin Tech.
3. In the Generate admin-tech File window, limit the contents of the Admin Tech tar file if desired:
  - a. The Include Logs checkbox is selected by default. Deselect this checkbox to omit any log files from the compressed tar file. Log files are stored in the `/var/log/` directory on the local device.
  - b. Select the Include Cores checkbox to include any core files. Core files are stored in the `/var/crash` directory on the local device.
  - c. Select the Include Tech checkbox to include any files related to device processes (daemons) and operations. These files are stored in the `/var/tech` directory on the local device.
4. Click Generate. A tar file is created which contains the contents of various files on the local device. This file has a name similar to `20150709-032523-admin-tech.tar.gz`, where the numeric fields are the date and time.
5. Send the `admin-tech.tar.gz` file to your Viptela customer support contact.

## Interface Reset Command

Use the Interface Reset command to shutdown and then restart an interface on a device in a single operation, without having to modify the device's configuration.

1. From the device table, select the device.
2. Click the More Actions icon to the right of the row and click Interface Reset.
3. In the Interface Reset window, select the desired interface.
4. Click Reset.

## Rediscover Network

Use the Rediscover Network screen to locate new devices in the overlay network and synchronize them with the vManage NMS.

## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Rediscover Network.
- Rows Selected—Displays the number of rows selected from the table.
  - Rediscover button—Click to rediscover the devices in the network.
- Device Groups drop-down—Lists all configured device groups in the network.
- Search box—Includes the Search Options drop-down, for a Contains or Match string.
- Refresh icon—Click to refresh data in the device table with the most current data.
- Show Table Fields icon—Click to display or hide columns from the device table. By default, all columns are displayed.
- Table of devices in the overlay network—To re-arrange the columns, drag the column title to the desired position.

Device Model	Hostname	System IP	Data Collection Stat...	Sync Started/Queued	Sync Completed	Reachability
<input type="checkbox"/> vManage	vm12	172.16.255.22	Completed	26 Jun 2018 11:06:47 AM PDT	26 Jun 2018 11:07:24 AM PDT	reachable
<input type="checkbox"/> vSmart	vm10	172.16.255.20	Completed	26 Jun 2018 11:06:49 AM PDT	26 Jun 2018 11:07:29 AM PDT	reachable
<input type="checkbox"/> vSmart	vm9	172.16.255.19	Completed	26 Jun 2018 11:07:38 AM PDT	26 Jun 2018 11:07:49 AM PDT	reachable
<input checked="" type="checkbox"/> vEdge Cloud	vm16	172.16.255.26	Completed	26 Jun 2018 4:12:54 AM PDT	26 Jun 2018 4:12:55 AM PDT	reachable
<input type="checkbox"/> vEdge 1000	C1111-8P	172.16.255.138	Completed	05 Jun 2018 4:11:13 PM PDT	05 Jun 2018 5:11:26 PM PDT	unreachable
<input type="checkbox"/> CSR1000v	CSR-cEdge1	172.16.255.130	Completed	26 Jun 2018 3:03:09 PM PDT	26 Jun 2018 3:03:11 PM PDT	reachable
<input type="checkbox"/> CSR1000v	CSR-cEdge2	172.16.255.134	Completed	26 Jun 2018 11:06:52 AM PDT	26 Jun 2018 11:07:25 AM PDT	reachable
<input type="checkbox"/> ISR4221	ISR4221	172.16.255.139	Completed	26 Jun 2018 3:03:09 PM PDT	26 Jun 2018 3:03:11 PM PDT	reachable
<input type="checkbox"/> ISR4331	ISR4331-SDW...	172.16.255.129	Completed	22 May 2018 6:19:56 AM PDT	22 May 2018 2:26:01 PM PDT	unreachable
<input type="checkbox"/> vEdge Cloud	vm1	172.16.255.11	Completed	26 Jun 2018 11:07:24 AM PDT	26 Jun 2018 11:07:32 AM PDT	reachable
<input type="checkbox"/> vEdge Cloud	vm11	172.16.255.21	Completed	26 Jun 2018 11:07:24 AM PDT	26 Jun 2018 11:07:32 AM PDT	reachable
<input type="checkbox"/> vEdge Cloud	vm4	172.16.255.14	Completed	26 Jun 2018 11:06:48 AM PDT	26 Jun 2018 11:07:32 AM PDT	reachable

## Rediscover the Network

To locate new devices in the overlay network, click the Rediscover button located directly beneath the title bar. vManage NMS rediscovers every device and link and displays updated information about the network.

## Synchronize Device Data

To synchronize the data on a specific device with the vManage NMS:

1. From the Device Groups drop-down list, select the device group to which the device belongs. The device table lists all the devices in the selected group.
2. Select the device.
3. Click the Rediscover button.
4. In the Rediscover Network window, click Rediscover to confirm re-synchronization of the device data.


## SSH Terminal

Use the SSH Terminal screen to establish an SSH session to a Viptela device. From an SSH session, you can issue CLI commands on the Viptela device.



## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vManage menu, and the vManage product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, SSH Terminal.
- Left pane—Includes:
  - Device Groups drop-down—Lists all configured device groups in the network.
  - Search box—Includes the Search Options drop-down, for a Contains or Match string.
  - Sort by drop-down options. You can sort the device list by reachability, hostname, system IP, site ID, or device model.
  - List of all Viptela devices in the selected device group.
- Right pane—Includes:
  - An open SSH window. The size of the window is based on the current browser size, and it does not readjust if you change the window size. A vertical scroll bar allows you to scroll up and down in the SSH window.



## Establish an SSH Session to a Device

To establish an SSH session to a device:

1. From the left pane, select the device on which to collect statistics:
  - a. Select the device group to which the device belongs.
  - b. If needed, sort the device list by its status, hostname, system IP, site ID, or device type.
  - c. Click on the device to select it.
2. Enter the username and password to log in to the device.

## Tools

You can now issue CLI commands to monitor or configure the device.

## vAnalytics

### Applications

Use the Applications screen to monitor application families and individual applications in your overlay network over time.

### Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vAnalytics menu, and the vAnalytics product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Applications.
  - Time Period—Click a predefined or custom time period for which to display data.
- Bandwidth—Displays bandwidth utilization for application families.
- Performance—Displays Viptela Quality of Experience (vQoE) values for application families. The vQoE value ranges from zero to ten, with zero being the worst performance and ten being the best. vQoE calculates this value based on latency, loss, and jitter, customizing the calculation for each application.
- Anomaly—Displays application families using more bandwidth than their baseline.



### Display Bandwidth Utilization

To display bandwidth utilization for application families:

1. Click Bandwidth.
2. Click the Filter icon to select a specific application family to view.
3. Click the PDF icon to open a PDF version of the chart in a new tab.

4. Hover over an item in any chart to open a hover box with details about that item.
5. Select a view: By Summary, By Time, or By Sites:
  - By Summary displays a summary by application family. Click an application family to display applications in that family. Click an application to see that application's bandwidth utilization over time. Click a point on the timeline to see that application's bandwidth utilization by site. Click a site to see flows for that application at that site.
  - By Time displays a timeline of application family bandwidth utilization. Click an application family to display utilization for the applications in that family. Click an application to display utilization at each site running the application. Click a site to display flows for that application at that site.
  - By Sites displays bandwidth utilization on each vEdge router. Click a site to display a timeline of application family bandwidth utilization at that site. Click an application family to display utilization for applications in that family at that time. Click an application to display flows for that application at that site.

## Display vQoE Values

To display vQoE values for each application family:

1. Click Performance.
2. Click the Filter icon to select a specific application family to view.
3. Click the PDF icon to open a PDF version of the chart in a new tab.
4. Hover over an application family in the chart to open a hover box with details for that application family.
5. Click an application family to display average latency, loss, jitter, and vQoE for each application in that family:
  - a. Click an application to display that application's performance on each device in the tunnel.
  - b. Click a device to display an hourly summary of that application on that device.

## Display Deviations from Baseline Utilization

vAnalytics platform computes daily averages and standard deviations for application families at every site in a rolling window of seven days. An anomaly occurs if an application family's bandwidth utilization exceeds the average plus two times the standard deviation.

To display deviations from baseline values of bandwidth utilization for application families:


1. Click Anomaly.
2. Click the Filter icon to select a specific application family to view.
3. Click the PDF icon to open a PDF version of the chart in a new tab.
4. Hover over an application family in the chart to open a hover box with details for that application family.
5. Click a site to see a timeline of anomalies for that site.
6. Click an hour on the timeline to see anomalous behavior of individual applications in that hour.

## Network Availability

Use the Network Availability screen to monitor downtime of nodes and circuits in your overlay network over time.

## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vAnalytics menu, and the vAnalytics product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Network Availability.
  - Time Period—Click a predefined or custom time period for which to display data.
- Selected View—Displays downtime by sites or by time.
- Summary—Displays node and circuit downtime summaries.



## Display Downtime by Site

To display vEdge router and circuit downtime for each site:

1. Select Aggregated Downtime by Sites.
2. Click the Filter icon to select specific application family to view.
3. Click the PDF icon to open a PDF version of the chart in a new tab.
4. Click a vEdge router or circuit to display details about that downtime event.

## Display Downtime by Time

To display vEdge router and circuit downtime for a specified time period:

1. Select Aggregated Downtime by Time.
2. Select a length of time: Day, Week, Quarter, or Year.
3. Click the Filter icon to select specific device or circuit to view.


4. Click the PDF icon to open a PDF version of the chart in a new tab.
5. Click a vEdge router or circuit to display details about that downtime event.

## Network Health

Use the Network Health screen to monitor the performance of circuits, tunnels, and carriers in your overlay network over time.

## Screen Elements

- Top bar—On the left are the menu icon, for expanding and collapsing the vAnalytics menu, and the vAnalytics product name. On the right are a number of icons and the user profile drop-down.
- Title bar—Includes the title of the screen, Network Health.
  - Tunnel—Displays latency, loss, and jitter by circuit.
  - Carrier—Displays application performance by carrier on a geographical map of your overlay network.
  - Time Period—Click a predefined or custom time period for which to display data.



## Display Latency, Loss, and Jitter on Circuits

To display graphs for latency, loss, and jitter on each circuit in your overlay network:

1. Click Tunnel. Each line in the graphs indicates one circuit. The legend to the right indicates the color of each circuit.
2. Click the Filter icon to select specific circuits to view.
3. Click the PDF icon to open a PDF version of the graph in a new tab.
4. Hover over a point on a line to open a hover box with details for that point in time.

5. Click a point on a line to display average latency, loss, or jitter in that circuit at that point in time:
  - a. Click a site to see latency, loss, or jitter for all tunnels at that site.
  - b. Click a tunnel to see hourly latency, loss, or jitter for that tunnel.
  - c. Click Overview to return to Network Health ► Tunnel.
6. To highlight specific circuits:
  - a. Click a circuit in the legend to select it. To select more than one circuit, hold down the Shift key.
  - b. Click the Highlight icon that appears. The selected circuits are highlighted on the map.
  - c. To display all circuits again, click the Highlight icon.

## Display Application Performance by Carrier

To display application performance by carrier on a geographical map of the overlay network:

1. Click Carrier. Circles on the map represent each carrier. The legend to the right indicates the color of each carrier.
2. Select Latency, Loss, or Jitter to change the data displayed.
3. Click the Filter icon to select specific carriers to view.
4. Click the PDF icon to open a PDF version of the map in a new tab.
5. Hover over a carrier's circle to display a hover box with details for that location.
6. Click a circle on the map to display that location's performance by loss, latency, or jitter:
  - a. Click a point on the graph to see a graph of performance for each carrier at that location.
  - b. Click a carrier to see performance for each vEdge router at that site.
  - c. Click a vEdge router to see that device's performance over time.
  - d. Click Overview to return to Network Health ► Carrier.
7. Hover over the map to display map functions:
  - a. Click Search to search for a geographical location by name.
  - b. Click the + (plus) or - (minus) zoom icons to zoom in or out.
  - c. Click Home to return to the world-wide view.
  - d. Hover over the right arrow for other map functions, such as selecting a zoom area and panning.
8. To highlight specific carriers:
  - a. Click a carrier in the legend to select it. To select more than one carrier, hold down the Shift key.
  - b. Click the Highlight icon that appears. The selected carriers are highlighted on the map.
  - c. To display all carriers again, click the Highlight icon.


## vAnalytics Dashboard

Use the vAnalytics dashboard screen to monitor the performance of the entire Viptela overlay network over time.

## Top Bar

The top bar is located at the top of every vAnalytics screen and includes the following screen elements:

- Menu icon—Click the icon to expand or collapse the vAnalytics menu. The vAnalytics menu is closed by default.
- vAnalytics product name.
- Help—Links to product help and software version information about the vAnalytics platform.
- vAnalytics username—Username for the vAnalytics platform that you are logged into. Includes the sign-out button.



## Network Availability Pane

The Network Availability pane displays network-wide availability for the last 24 hours by device and circuit. Each box displays uptime as a percentage and total downtime in minutes.

Click in the Device box to display downtime for each vEdge router in the overlay network. Click in the Circuit box to display downtime for each circuit in the overlay network.

- Click the Filter icon to select a specific vEdge router or circuit to view.
- Click the PDF icon to open a PDF version of the chart in a new tab.
- Click any bar to display the time period when that device or circuit was down.

## Applications Pane

The Applications Pane displays application performance for the last 24 hours in three views: Least Performing Applications, Applications Consuming Most Bandwidth, and Anomalous Application Families.



## Least Performing Applications

The Least Performing Applications box displays the applications in the network with the lowest performance.

vAnalytics platform calculates application performance with the Viptela Quality of Experience (vQoE) value. This value ranges from zero to 10, with zero being the worst performance and 10 being the best. vQoE combines scores for latency, loss, and jitter, customizing the calculation for the needs of each application.

- Select vQoE, Latency, Loss, or Jitter to change the data displayed.
- Click the Sort icon to toggle between Least Performing Applications and Top Performing Applications.
- Click the PDF icon to open a PDF version of the chart in a new tab.
- Hover over a bar in the graph to open a hover box with details about that application.
- Click a bar in the graph to display that application's performance on each tunnel. Click a tunnel to display the application's hourly performance on that tunnel.

## Applications Consuming Most Bandwidth

The Applications Consuming Most Bandwidth box displays applications consuming the most bandwidth in the network.

Each circle represents an application; the larger the circle, the greater is the bandwidth that it consumes. The legend to the right indicates the color of each application family. The graph displays the top ten applications using the most bandwidth, and an additional circle called Others. Click Others for details about any remaining applications.

- Click the PDF icon to open a PDF version of the graph in a new tab.
- Hover over a circle in the graph to open a hover box with details about that application.
- Click a circle in the graph to display that application's bandwidth consumption over time. Click a point on the graph to display sites using that application. Click a site to display flows for that site.
- To highlight specific application families:
  - a. Click a family in the legend to select it. To select more than one family, hold down the Shift key.
  - b. Click the Highlight icon that appears. The selected carriers are highlighted on the map.
  - c. To display all families again, click the Highlight icon.

## Anomalous Application Families

The Anomalous Application Families box displays application families using more bandwidth than their baseline.

- Click the PDF icon to open a PDF version of the chart in a new tab.
- Hover over a bar in the graph to display a hover box with details about that application family.
- Click a bar in the graph to display that family's average octets by site. Click a bar in the graph to display that site's octets over time for that family. Click a bar in the timeline to display octets at that point in time for each application in the family.

## WAN Performance Pane

The WAN Performance pane displays performance of carriers and tunnels for the last 24 hours by latency, loss, or jitter.

### Carrier Performance

The Carrier Performance box displays application performance by carrier on a geographical map of the overlay network.

Circles on the map represent each carrier. The legend to the right indicates the color of each carrier.

- Select Latency, Loss, or Jitter to change the data displayed.
- Click the PDF icon to open a PDF version of the map in a new tab.
- Hover over a carrier's circle to display a hover box with details for that location.
- Click a circle on the map to display that location's performance for the last 24 hours in graphical format. Hover over a point on the graph for details about that point in time.
- Hover over the map to display map functions:
  - Click Search to search for a geographical location by name.
  - Click the + (plus) or – (minus) zoom icons to zoom in or out.
  - Click Home to return to the world-wide view.
  - Hover over the right arrow for other map functions, such as selecting a zoom area and panning.
- To highlight specific carriers:
  - a. Click a carrier in the legend to select it. To select more than one carrier, hold down the Shift key.
  - b. Click the Highlight icon that appears. The selected carriers are highlighted on the map.
  - c. To display all carriers again, click the Highlight icon.

### Tunnel Performance

The Tunnel Performance box displays the performance of tunnels for the last 24 hours by latency, loss, or jitter. The legend to the right indicates the color of each tunnel.

- Select Latency, Loss, or Jitter to change the data displayed.
- Click the PDF icon to open a PDF version of the chart in a new tab.
- Hover over a point on the graph to display a hover box with details about that point in time.
- To highlight specific tunnels:
  - a. Click a tunnel in the legend to select it. To select more than one tunnel, hold down the Shift key.
  - b. Click the Highlight icon that appears. The selected tunnels are highlighted on the graph.
  - c. To display all tunnels again, click the Highlight icon.

## vManage NMS Product Help

The vManage NMS is a centralized network management system that provides a GUI interface to easily monitor, configure, and maintain all Viptela devices and links in the overlay network. The vManage NMS software runs on a server in the network.

### Browser Support

You can access the vManage NMS using the Chrome and Firefox browsers.

You can access the vManage NMS from VPN 0 (the WAN transport VPN) and from VPN 512 (the management VPN).

### vManage Dashboard

When you log into the vManage NMS, the dashboard provides a quick summary of the network.

Here, at a glance, you can view the health of the entire network including the operational state of any device, total number of reboots and crashes, and the state of all controller certificates. This visibility into the network eases the task of managing the Viptela devices.

### vManage Menu

As shown in the above figure, the menu is located to the left of the Dashboard screen. The following table lists each menu and sub-menu item and provides a brief description.

Menu Item

Description

#### **Dashboard**

##### [Dashboard](#)

Monitor, at a glance, the health of the Viptela overlay network.

#### **Monitor**

##### [Geography](#)

A map view of the entire network and displays the geographic location of the devices in the network.

##### [Network](#)

An inventory of all Viptela devices in the network along with detailed information on each device.

##### [Alarms](#)

Details on alarms generated by all Viptela devices in the network.

##### [Events](#)

Details on events generated by all Viptela devices in the network.

##### [Audit Log](#)

An audit log of all activities on Viptela devices.

#### **Configuration**

### [Devices](#)

Add or delete devices from the overlay network.

### [Certificates](#)

Manage certificates and authenticate Viptela devices in the overlay network.

### [Templates](#)

Create configuration templates for a set of Viptela devices.

### **Policy**

Create common policies for a set of vSmart controllers.

### **Tools**

#### [SSH Terminal](#)

Establish an SSH session to a Viptela device.

#### [Rediscover Network](#)

Locate new devices in the overlay network and synchronize them with the vManage NMS.

#### [Operational Commands](#)

Run two or more operational commands as a single command.

### **Maintenance**

#### [Software Upgrade](#)

Download new software images and upgrade the software image running on Viptela devices.

#### [Device Reboot](#)

Reboot one or more Viptela devices.

### **Administration**

#### [Settings](#)

Configure organization name and certificate authorization settings.

#### [Manage Users](#)

Add, edit, or delete users and user groups from the vManage NMS.

## Bringing Up the Viptela Overlay Network

The following table lists the tasks for bringing up the Viptela overlay network using the vManage NMS.


Bringup Task	Step-by-Step Procedure
--------------	------------------------

<p>Step 1: Start the vManage NMS</p>	<ol style="list-style-type: none"> <li>1. On the hypervisor, create a VM instance.</li> <li>2. Boot the vManage NMS server, start the VM, and enter login information.</li> <li>3. In vManage ► Administration ► Settings, configure certificate authorization settings. Select Automated to allow the certificate-generation process to occur automatically when a CSR is generated for a controller device.</li> <li>4. In vManage ► Certificates, generate the CSR.</li> <li>5. Check for a confirmation email from Symantec that your request has been received.</li> <li>6. Check for an email from Symantec that Viptela has approved your request and the certificate is signed.</li> <li>7. In vManage ► Configuration ► Devices, check that the certificate has been installed.</li> </ol>
<p>Step 2: Start the vBond orchestrator</p>	<ol style="list-style-type: none"> <li>8. On the hypervisor, create a VM instance.</li> <li>9. Boot the vBond server and start the VM.</li> <li>10. In vManage ► Configuration ► Devices ► Controller, add the vBond orchestrator and generate the CSR.</li> <li>11. Check for a confirmation email from Symantec that your request has been received.</li> <li>12. Check for an email from Symantec that Viptela has approved your request and the certificate is signed.</li> <li>13. In vManage ► Configuration ► Devices, check that the certificate has been installed.</li> <li>14. In vManage ► Configuration ► Templates: <ol style="list-style-type: none"> <li>a. Create a configuration template for the vBond orchestrator.</li> <li>b. Attach the template to the vBond orchestrator.</li> </ol> </li> <li>15. In vManage ► Dashboard, verify that the vBond orchestrator is operational.</li> </ol>
<p>Step 3: Start the vSmart controller</p>	<ol style="list-style-type: none"> <li>16. On the hypervisor, create a VM instance.</li> <li>17. Boot the vSmart server and start the VM.</li> <li>18. In vManage ► Configuration ► Devices ► Controller, add the vSmart controller and generate the CSR.</li> <li>19. Check for a confirmation email from Symantec that your request has been received.</li> <li>20. Check for an email from Symantec that Viptela has approved your request and the certificate is signed.</li> <li>21. In vManage ► Configuration ► Devices, check that the certificate has been installed.</li> <li>22. In vManage ► Configuration ► Templates: <ol style="list-style-type: none"> <li>a. Create a configuration template for the vSmart controller.</li> <li>b. Attach the template to the vSmart controller.</li> </ol> </li> <li>23. In vManage ► Dashboard, verify that the vSmart controller is operational.</li> </ol>

Step 4: Configure the vEdge router	<p>24. In vManage ► Configuration ► Devices ► vEdge List, upload the vEdge authorized serial number file.</p> <p>25. In vManage ► Configuration ► Certificates ► vEdge List, check that the router's chassis and serial number are in the vEdge list.</p> <p>26. In vManage ► Configuration ► Certificates ► vEdge List, authorize each router by marking it Valid in the Validity column.</p> <p>27. In vManage ► Configuration ► Certificates ► vEdge List, send the vEdge list to the controller devices.</p> <p>28. In vManage ► Configuration ► Templates:</p> <ul style="list-style-type: none"> <li>a. Create a configuration template for the vEdge router.</li> <li>b. Attach the template to the vEdge router.</li> </ul>
Step 5: Connect AC power and boot the vEdge router	<p>29. Connect AC power to the vEdge router.</p> <p>30. If needed, flip the On/Off switch on the rear of the router to the ON position.</p> <p>31. In vManage ► Dashboard or in vManage ► Monitor ► Network ► Device Dashboard, verify that the vEdge router is operational.</p>

## RESTful API for vManage NMS

The vManage NMS supports a RESTful (Representational State Transfer) API, which provides calls for retrieving real-time and static information about the Viptela overlay network and the devices in the network and for uploading device configuration templates and other configuration-related information. Using the RESTful API, you can design a custom portal for interacting with the vManage NMS.



The vManage API documentation is provided as part of the vManage software, at the URL <https://vmanage-ip-address/apidocs>. (More accurately, the full URL includes the vManage port number, <https://vmanage-ip-address:8443/apidocs>.) *vmanage-ip-address* is the IP address of the vManage server.

API calls are provided for the following categories of operations:

- Certificate Management
- Configuration
- Device and Device Inventory
- Monitoring
- Real-Time Monitoring
- Troubleshooting Tools

For each group of API calls, click Show/Hide to list the individual calls and the URL for each call. Each call shows its response class, required parameters, and response messages (status codes).

To display the request URL for each API call and the format of the response body, click the Try It Out button. The request URL consists of the vManage NMS's URL, followed by /dataservice. For example, <https://10.0.1.32:8443/dataservice/device/interface/statistics/ge0/0?deviceId=172.16.255.11>

Below are a few examples of the URLs to use for API calls:

Requested Information	API Call
List all network devices	<code>dataservice/device</code>
Health status of hardware device components, such as CPU, memory, fan, and power	<code>dataservice/device/hardware/environment?deviceId= system-ip-address</code>
Status of a device's transport interfaces	<code>dataservice/device/interface?deviceId= system-ip-address &amp;port-type=transport</code>
Interface statistics, errors, and packet drops	<code>dataservice/device/interface?deviceId= system-ip-address</code>
DTLS/TLS control connection status	<code>dataservice/device/control/connections?deviceId= system-ip-address</code>
OMP peering	<code>dataservice/device/omp/peers?deviceId= system-ip-address</code>
BGP peering on the service side	<code>dataservice/device/bgp/neighbors?deviceId= system-ip-address</code>