

# **UCC 5G SMF Release Notes, Release 2024.03.1**

First Published: 2024-08-21

# **5G Converged Core Session Management Function**

### Introduction

This Release Notes identifies changes and issues related to this software release.

## **Release Lifecycle Milestones**

| Release Lifecycle Milestone               | Milestone | Date        |
|---|-----------|-------------|
| First Customer Ship                       | FCS       | 31-Jul-2024 |
| End of Life                               | EoL       | 31-Jul-2024 |
| End of Software Maintenance               | EoSM      | 29-Jan-2026 |
| End of Vulnerability and Security Support | EoVSS     | 29-Jan-2026 |
| Last Date of Support                      | LDoS      | 31-Jan-2027 |

These milestones and the intervals between them are defined in the Cisco Ultra Cloud Core (UCC) Software Release Lifecycle Product Bulletin available on cisco.com.

## **Release Package Version Information**

| Software Packages     | Version                    |
|-----------------------|----------------------------|
| ccg-2024.03.1.SPA.tgz | 2024.03.1                  |
| NED package           | ncs-5.6.8-ccg-nc-2024.03.1 |
|                       | ncs-6.1-ccg-nc-2024.03.1   |
| NSO                   | 6.1.11                     |

Descriptions for the various packages provided with this release are available in the Release Package Descriptions section.

## **Verified Compatibility**

| Products             | Version      |
|----------------------|--------------|
| Ultra Cloud Core SMI | 2024.03.1.12 |

| Products             | Version   |
|----------------------|-----------|
| Ultra Cloud CDL      | 1.11.8.1  |
| Ultra Cloud Core UPF | 2024.03.0 |
| Ultra Cloud cnSGWc   | 2024.03.1 |

For information on the Ultra Cloud Core products, refer to the documents for this release available at:

- https://www.cisco.com/c/en/us/support/wireless/ultra-cloud-core-subscriber-microservices-infrastructure/ products-installation-and-configuration-guides-list.html
- https://www.cisco.com/c/en/us/support/wireless/ultra-cloud-core-user-plane-function/ products-installation-and-configuration-guides-list.html
- https://www.cisco.com/c/en/us/support/wireless/ultra-cloud-core-serving-gateway-function/products-installation-and-configuration-guides-list.html

## What's New in This Release

#### **Features and Enhancements**

This section covers a brief description of the features and enhancements introduced in this release. It also includes links to detailed documentation, where available.

| Feature  | Description   |
|--|---|
| Support for UE IP<br>Address Hold and<br>Reuse | This feature allows SMF to allocate the same IP address and session ID to a user session if the user reattaches within a configurable session hold timer after session release. |
|  | This feature improves the user experience and reduces the IP address exhaustion in scenarios where users frequently attach and detach.  |
|  | <b>New commands</b> : <b>session-hold duration</b> in Converged Core profile and DNN profile configurations   |

#### **Behavior Changes**

There are no behavior changes in this release.

#### **Related Documentation**

For the complete list of documentation available for this release, see https://www.cisco.com/c/en/us/support/wireless/ultra-cloud-core-session-management-function/products-installation-and-configuration-guides-list.html.


# **Installation and Upgrade Notes**

This Release Note does not contain general installation and upgrade instructions. Refer to the existing installation documentation for specific installation and upgrade considerations.

### **Software Integrity Verification**

To verify the integrity of the software image you have from Cisco, you can validate the SHA512 checksum information against the checksum identified by Cisco for the software.

Image checksum information is available through **Cisco.com Software Download Details**. To find the checksum, hover the mouse pointer over the software image you have downloaded.



At the bottom you find the SHA512 checksum, if you do not see the whole checksum you can expand it by pressing the "..." at the end.

To validate the information, calculate a SHA512 checksum using the information in Table 1: Checksum Calculations per Operating System and verify that it matches either the one provided on the software download page.

To calculate a SHA512 checksum on your local desktop, refer to the table below.

Table 1: Checksum Calculations per Operating System

| Operating System                             | SHA512 checksum calculation command examples               |
|--|--|
| Microsoft Windows                            | Open a command line window and type the following command: |
|  | > certutil.exe -hashfile filename.extension SHA512         |
| Apple MAC                                    | Open a terminal window and type the following command:     |
|  | \$ shasum -a 512 filename.extension                        |
| Linux  | Open a terminal window and type the following command:     |
|  | \$ sha512sum filename.extension                            |
|  | OR   |
|  | \$ shasum -a 512 filename.extension                        |
| <b>Note</b> filename is the name of the file | e.   |
| extension is the file extension              | (for example, .zip or .tgz).                               |

If the SHA512 checksum matches, you can be sure that no one has tampered with the software image or the image has not been corrupted during download.

If the SHA512 checksum does not match, we advise you to not attempt upgrading any systems with the corrupted software image. Download the software again and verify the SHA512 checksum again. If there is a constant mismatch, please open a case with the Cisco Technical Assistance Center.

#### **Certificate Validation**

SMF software images are signed via x509 certificates. Please view the .README file packaged with the software for information and instructions on how to validate the certificates.

## **Open Bugs for this Release**

The following table lists the open bugs in this specific software release.



Note

This software release may contain open bugs first identified in other releases. Additional information for all open bugs for this release are available in the Cisco Bug Search Tool.

| Bug ID     | Headline                                      |
|------------|---|
| CSCwk65884 | SMF-LI: Encrypt all the CALEA Data in ETCD DB |

# **Resolved Bugs for this Release**

The following table lists the resolved bugs in this specific software release.

| Bug ID     | Headline   | Behavior Change |
|------------|--|-----------------|
| CSCwk85890 | CDL - some updates are missed during GR shut/start                                   | No              |
| CSCwm26634 | Memory leak observed with multiple pods in smf during longevity run                  | No              |
| CSCwm26988 | Incorrect rat-type populating in cdl session-type for 5G Roamer post rolling upgrade | No              |

## **Operator Notes**

### **Cloud Native Product Version Numbering System**

The show helm list command displays detailed information about the version of the cloud native product currently deployed.

### Versioning: Format & Field Description

### YYYY.RN.MN[.TTN] [.dN] [.MR][.iBN]

### Where,

#### YYYY → 4 Digit year.

- Mandatory Field.
- Starts with 2020.
- · Incremented after the last planned release of year.

#### RN → Major Release Number.

- Mandatory Field.
- Starts with 1.
- Support preceding 0.
- · Reset to 1 after the last planned release of a year(YYYY).

#### MN→ Maintenance Number.

- Mandatory Field.
- Starts with 0.
- · Does not support preceding 0.
- Reset to 0 at the beginning of every major release for that release
- · Incremented for every maintenance release.
- Preceded by "m" for bulbs from main branch.

#### TTN → Throttle of Throttle Number.

- · Optional Field, Starts with 1.
- Precedes with "t" which represents the word "throttle or throttle".
- · Applicable only in "Throttle of Throttle" cases.
- Reset to 1 at the beginning of every major release for that release.

#### DN -> Dev branch Number

- Same as TTN except Used for DEV branches.
- · Precedes with "d" which represents "dev branch".

#### MR → Major Release for TOT and DEV branches

- · Only applicable for TOT and DEV Branches.
- · Starts with 0 for every new TOT and DEV branch.

#### BN -> Build Number

- · Optional Field, Starts with 1.
- Precedes with "t" which represents the word "interim".
- · Does not support preceding 0.
- Reset at the beginning of every major release for that release.
- Reset of every throttle of throttle.

523483

The appropriate version number field increments after a version has been released. The new version numbering format is a contiguous sequential number that represents incremental changes between releases. This format facilitates identifying the changes between releases when using Bug Search Tool to research software releases.

### **Release Package Descriptions**

The following table provides descriptions for the packages that are available with this release.

Table 2: Release Package Information

| Software Packages  | Description   |
|--|---|
| ccg. <version>.SPA.tgz</version>                                   | The SMF offline release signature package. This package contains the SMF deployment software, NED package, as well as the release signature, certificate, and verification information. |
| ncs- <nso_version>-ccg-nc-<version>.tar.gz</version></nso_version> | The NETCONF NED package. This package includes all the yang files that are used for NF configuration.   |
|  | Note that NSO is used for the NED file creation.  |

## **Obtaining Documentation and Submitting a Service Request**

For information on obtaining documentation, using the Cisco Bug Search Tool (BST), submitting a service request, and gathering additional information, refer to <a href="https://www.cisco.com/c/en/us/support/index.html">https://www.cisco.com/c/en/us/support/index.html</a>.