Configure Single Sign-On with CUCM and AD FS 2.0

Contents

Introduction
Prerequisites
Requirements
Components Used
Background Information
Download and Install AD FS 2.0 on your Windows Server
Configure AD FS 2.0 on Your Windows Server
Import the IdP Metadata to CUCM / Download the CUCM Metadata
Import CUCM Metatdata to AD FS 2.0 Server and Create Claim Rules
Finish SSO Enablement On CUCM And Run The SSO Test
Troubleshoot
Set SSO Logs to Debug
Find The Federation Service Name
Dotless Certificate And Federation Service Name
Time is Out of Sync between the CUCM and IdP Servers
<u>Related Information</u>

Introduction

This document describes how to configure Single Sign-On (SSO) on Cisco Unified Communications Manager and Active Directory Federation Service.

Prerequisites

Requirements

Cisco recommends that you have knowledge of these topics:

- Cisco Unified Communications Manager (CUCM)
- Basic Knowledge of Active Directory Federation Service (AD FS)

In order to enable SSO in your lab environment, you need this configuration:

- Windows Server with AD FS installed.
- CUCM with LDAP sync configured.
- An End User with the Standard CCM Super Users role selected.

Components Used

The information in this document is based on these software and hardware versions:

- Windows Server with AD FS 2.0
- CUCM 10.5.2

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, ensure that you understand the potential impact of any command.

Background Information

The procedure for AD FS 2.0 with Windows Server 2008 R2 is provided. These steps also work for AD FS 3.0 on Windows Server 2016.

Download and Install AD FS 2.0 on your Windows Server

- Step 1. Navigate to Download AD FS 2.0.
- Step 2. Ensure that you select the appropriate download based on your Windows Server.
- Step 3. Move the downloaded file to your Windows Server.
- Step 4. Proceed with the installation:
- Step 5. When prompted, choose Federation Server:

Active Directory Federation Services 2.0	Setup Wizard
Server Role	
 one of the following roles for this computer. Federation server A federation server is an authentication an enable access to claims-based application Federation server proxy A federation server proxy redirects request 	eration server role or the federation server proxy role. Select of trust management provider that issues security tokens to is in your organization or in federated partner organizations. s from Internet clients to federation servers that are behind a forwards security tokens issued by federation servers to
	< Previous Next > Cancel


Step 6. Some dependencies are automatically installed. Once that is done, click Finish.

Now that you have AD FS 2.0 installed on your server, you need to add some configuration.


Configure AD FS 2.0 on Your Windows Server

Step 1. If the AD FS 2.0 window did not automatically open after the install, click **Start** and search for AD FS 2.0 Management to open it manually.


Step 2. Choose AD FS 2.0 Federation Server Configuration Wizard.



Step 3. Next, click Create a new Federation Service.



Step 4. For most environments, Stand-alone federation server is sufficient.



Step 5. Next, you are asked to choose a certificate. This field auto-populates as long as the server has a certificate.

iteps	This wizard determines the Federation Service	e name from th	ne Subiect fiel	d of the S	SL certificate for the	в
Welcome Select Deployment Type	Default Web Site. If the wizard cannot deter must select a certificate. Select the certificate and/or port, and then c	mine the Fede				
Federation Service Name	SSL certificate:	ICK IVEXL.		Port:		
Existing Database	sso.win2k8	*	View	443	*	
 Summary Results 	Federation Service name:					
	Win2k8.sckiewer.lab	*				

Step 6. If you already have an AD FS database on the server, you need to remove it to continue.

Step 7. Finally, you are on a summary screen where you can click Next.

Import the IdP Metadata to CUCM / Download the CUCM Metadata

Step 1. Update the URL with your Windows server hostname/FQDN and download the metadata from your AD FS server - <u>https://hostname/federationmetadata/2007-06/federationmetadata.xml</u>

Step 2. Navigate to Cisco Unified CM Administration > System > SAML Single Sign-On.

Step 3. Click Enable SAML SSO.

Step 4. If you receive an alert about Web Server Connections, click Continue.

Step 5. Next, CUCM instructs you to download the metadata file from your IdP. In this scenario, your AD FS server is the IdP, and you downloaded the metadata in Step 1, so click **Next**.

Step 6. Click **Browse** > **Select the .xml from Step 1** > Click **Import IdP Metadata**.

Step 7. A message indicates that the import was successful:

System 🔻 Call	Routing 🔻 Medi	a Resources 🔻	Advanced Featu	ires 🔻 De	vice 🔻	Application	 User Management
AML Single	Sign-On Confi	guration					
Next							
Status							
√ Import s	ucceeded for all	servers					
Import the I	dP Metadata T	rust File —					
This step uplo	ads the file acqu	ired from the	IdP in the prev	ous manua	al step to	the Collab	ooration servers.
1)Select the I File	dP Metadata Tru	st					
Browse N	No file <mark>s</mark> elected.						
2)Import this	file to the Collat	oration serve	rs				
This action m	ust be successfu	l for at least t	ne Publisher bef	ore moving	g on to t	n <mark>e n</mark> ext tas	k in this wizard.
Import Id	P Metadata	V 1	mport succeede	ed for all se	ervers		

Step 8. Click Next.

Step 9. Now that you have the IdP metadata imported into CUCM, you need to import CUCM's metadata into your IdP.

Step 10. Click Download Trust Metadata File.

Step 11. Click Next.

Step 12. Move the .zip fileto your Windows Server and extract the contents to a folder.

Import CUCM Metatdata to AD FS 2.0 Server and Create Claim Rules

Step 1. Click Start and search for AD FS 2.0 Management.

Step 2. Click Required: Add a trusted relying party.

Note: If you do not see this option, you need to close the window and open it back up.

Step 3. Once you have the Add Relying Party Trust Wizard open, click Start.

Step 4. Here, you need to import the XML files that you extracted in step 12. Select **Import data about the relying party from a file** and browse to the folder files and choose the XML for your publisher.

Note: Use the previous steps for any Unified Collaboration server on which you intend to utilize SSO.

Steps	Select an option that this wizard will use to obtain data about this relving party:
 Welcome Select Data Source Specify Display Name Choose Issuance Authorization Rules Ready to Add Trust Finish 	Select an option that this wizard will use to obtain data about this relying party: Import data about the relying party published online or on a local network. Use this option to import the necessary data and certificates from a relying party organization that publishes its federation metadata online or on a local network. Federation metadata address (host name or URL): Example: fs.contoso.com or https://www.contoso.com/app Import data about the relying party from a file Use this option to import the necessary data and certificates from a relying party organization that has exported its federation metadata to a file. Ensure that this file is from a trusted source. This wizard will not validate the source of the file. Federation metadata file location: C:\Users\Administrator\Desktop\SPMetadata_1cucm1052.sckiewer.lab.xml Browse C Enter data about the relying party manually Use this option to manually input the necessary data about this relying party organization.

Step 5. Click Next.

Step 6. Edit the **Display Name** and click **Next**.

Step 7. Choose **Permit all users to access this relying party** and click **Next**.

Step 8. Click Next again.

Step 9. On this screen, ensure that you have **Open the Edit Claim Rules dialog for this relying party trust when the wizard closes** checked, then click **Close**.

Step 10. The Edit Claim Rules window opens:

Order	Rule Name		Issued Claims	
				1
Add R	ule	Remove Rul	e	

Step 11. In this window, click **Add Rule**.

- Step 12. For Claim rule template, choose Send LDAP Attributes as Claims and click Next.
- Step 13. On the next page, enter NameID for the Claim rule name.
- Step 14. Choose Active Directory for the Attribute store.
- Step 15. Choose SAM-Account-Name for the LDAP Attribute.

Step 16. Enter uid for Outgoing Claim Type.

Note: uid is not an option in the drop down list - it must be entered manually.

📬 Add Transform Claim R	tule Wizard					D
Configure Rule						
Steps Choose Rule Type Configure Claim Rule	which issued Claim Name Rule t	an configure this rule to send the to extract LDAP attributes. Spe I from the rule. rule name: ID emplate: Send LDAP Attributes ate store:	cify how the attri	P attributes as claims. S butes will map to the or	Select an attribute utgoing claim type:	store from s that will be
		e Directory ing of LDAP attributes to outgoir	ng claim types:	•		
		LDAP Attribute	0	utgoing Claim Type		
		SAM-Account-Name	uic	1		
	▶*					
			< Previo	us Finish	Cancel	Help

Step 17. Click Finish.

Step 18. The first rule is now finished. Click Add Rule again.

Step 19. Choose Send Claims Using a Custom Rule.

Step 20. Enter a **Claim rule name**.

Step 21. In the **Custom rule** field, paste this text:

c:[Type == "http://schemas.microsoft.com/ws/2008/06/identity/claims/windowsaccountname"] => issue(Type = "http://schemas.xmlsoap.org/ws/2005/05/identity/claims/nameidentifier", Issuer = c.Issuer, OriginalIssuer = c.OriginalIssuer, Value = c.Value, ValueType = c.ValueType,Properties["http://schemas.xmlsoap.org/ws/2005/05/identity/claimproperties/format"] = "urn:oasis:names:tc:SAML:2.0:nameidformat:transient",Properties["http://schemas.xmlsoap.org/ws/2005/05/identity/claimproperties/namequalifier"] = "http://ADFS_FEDERATION_SERVICE_NAME/com/adfs/service/trust", Properties["http://schemas.xmlsoap.org/ws/2005/05/identity/claimproperties/spnamequalifier"] = "CUCM_ENTITY_ID");

Step 22. Ensure that you change AD_FS_SERVICE_NAME and CUCM_ENTITY_ID to the appropriate values.

Note: If you are not sure about the AD FS Service Name, you can follow the steps to find it. The CUCM Entity ID can be pulled from first line in the CUCM metadata file. There is an entityID on the

first line of the file that looks like this, entityID=1cucm1052.sckiewer.lab,. You need to enter the underlined value into the appropriate section of the claim rule.

Steps	You can configure a custom claim rule, such as a rule that requires multiple incoming claims or that extracts
Choose Rule Type	claims from a SQL attribute store. To configure a custom rule, type one or more optional conditions and an issuance statement using the AD FS 2.0 claim rule language.
Configure Claim Rule	Claim rule name:
	CUCM SSO Custom Rule
	Rule template: Send Claims Using a Custom Rule
	Custom rule:
	<pre>=> issue(Type = "http://schemas.xmlsoap.org/ws/2005/05/identity/claims/nameidentifier ", Issuer = c.Issuer, OriginalIssuer = c.OriginalIssuer, Value = c.Value, ValueType = c.ValueType, Properties ["http://schemas.xmlsoap.org/ws/2005/05/identity/claimproperties/form at"] = "urn:oasis:names:tc:SAML:2.0:nameid-format:transient", Properties ["http://schemas.xmlsoap.org/ws/2005/05/identity/claimproperties/name qualifier"] = "http://win2k8.sckiewer.lab/adfs/com/adfs/service/trust", Properties ["http://schemas.xmlsoap.org/ws/2005/05/identity/claimproperties/name qualifier"] = "http://schemas.xmlsoap.org/ws/2005/05/identity/claimproperties/spna mequalifier"] = "lcucm1052.sckiewer.lab");</pre>
	More about the claim rule language

Step 23. Click Finish.

Step 24. Click OK.

Note: Claim rules are needed for any Unified Collaboration server on which you intend to utilize SSO.

Finish SSO Enablement On CUCM And Run The SSO Test

Step 1. Now that the AD FS server is fully configured, you can go back to CUCM.

Step 2. You left off at the final configuration page:

SAML Single Sign-On Configu	iration
Back	
Status	nust be installed on the IdP before this test is run.
Test SS0 Setup	
This test verifies that the metad	ata files are correctly configured and will allow SSO to start up on the servers. This test can be run on
1)Pick a valid username to use t	for this test
This user must have administrat	sword for the selected username. tor rights and also exist in the IdP. mames shown below. Using any other Username to log into the IdP may result in administrator lockout.
sckiewer	
2)Launch SSO test page Run SSO Test	
Back Cancel	

Step 3. Select your End User which has the **Standard CCM Super Users** role selected and click **Run SSO Test...**

Step 4. Ensure that your browser allows pop-ups, and enter your credentials into the prompt.



SSO Test Succeeded!

Congratulations on a successful SAML SSO configuration test. Please close this window and click "Finish" on the SAML configuration wizard to complete the setup.

Step 5. Click Close on the pop-up window, and then Finish.

Step 6. After a brief restart of the web applications, SSO is enabled.

Troubleshoot

Set SSO Logs to Debug

To set the SSO logs to debug, you have to run this command in the CLI of the CUCM: **set samltrace level debug**

The SSO logs can be downloaded from RTMT. The name of the log set is Cisco SSO.

Find The Federation Service Name

To find the federation service name, click Start and search for AD FS 2.0 Management.


- Click on Edit Federation Service Properties...
- While on the General tab, look for Federation Service name

Dotless Certificate And Federation Service Name


If you receive this error message in the AD FS configuration wizard, you need to create a new certificate.

The selected certificate cannot be used to determine the Federation Service name because the selected certificate has a dotless (short-named) Subject name. Select another certificate without a dotless (short-named) Subject name, and then try again.


Step 1. Click Start and search for iis, then open Internet Information Services (IIS) Manager



Step 2. Click your server name.



Step 3. Click Server Certificates.



Step 4. Click Create Self-Signed Certificate.



Step 5. Enter the name you want for the alias of your certificate.

Create Self	-Signed Certificate			? ×
P	Specify Friendly Name			
Specify a for signing	file name for the certificate request. g:	This information can be :	sent to a certificate authorit	у
Specify a	friendly name for the certificate:			
sso.win2k	:8.pkinane.lab		1	
			ОК	Cancel

Time is Out of Sync between the CUCM and IdP Servers

If you receive this error when you run the SSO test from CUCM, you need to configure the Windows Server to use the same NTP server(s) as the CUCM.

Invalid SAML response. This can be caused when time is out of sync between the Cisco Unified Communications Manager and IDP servers. Please verify the NTP configuration on both servers. Run "utils ntp status" from the CLI to check this status on Cisco Unified Communications Manager.

Once the Windows Server has the correct NTP servers specified, you need to perform another SSO test and see if the issue persists. In some instances, it is necessary to skew the validity period of the assertion. More detail on that process <u>here</u>.

Related Information

<u>Technical Support & Documentation - Cisco Systems</u>